

Photon Unity Networking
v1.82

Generated by Doxygen 1.8.7

Wed Apr 12 2017 15:19:50

Contents

1	Main Page	1
2	General Documentation	3
2.1	Photon	3
2.1.1	Master Server And Lobby	4
2.1.2	Remote Procedure Calls	7
2.1.3	Instantiating Networked Objects	8
3	Network Simulation GUI	13
4	Network Statistics GUI	15
5	Public API Module	17
6	Module Documentation	19
6.1	Public API	19
6.1.1	Detailed Description	21
6.1.2	Enumeration Type Documentation	21
6.1.2.1	ClientState	21
6.1.2.2	DisconnectCause	21
6.1.2.3	PhotonLogLevel	22
6.1.2.4	PhotonNetworkingMessage	22
6.1.2.5	PhotonTargets	26
6.1.3	Function Documentation	27
6.1.3.1	OnPhotonSerializeView	27
6.2	Optional Gui Elements	28
6.2.1	Detailed Description	28
7	Namespace Documentation	29
7.1	Package ExitGames	29
7.2	Package ExitGames.Client	29
7.3	Package ExitGames.Client.GUI	29
7.3.1	Enumeration Type Documentation	29
7.3.1.1	GizmoType	29

7.4	Package ExitGames.Client.Photon	30
7.5	Package ExitGames.Client.Photon.Chat	30
7.5.1	Enumeration Type Documentation	31
7.5.1.1	ChatDisconnectCause	31
7.5.1.2	ChatState	31
7.5.1.3	CustomAuthenticationType	32
7.6	Package Photon	32
7.6.1	Typedef Documentation	32
7.6.1.1	Hashtable	32
7.7	Package UnityEngine	32
7.8	Package UnityEngine.SceneManagement	33
8	Class Documentation	35
8.1	ActorProperties Class Reference	35
8.1.1	Detailed Description	35
8.1.2	Member Data Documentation	35
8.1.2.1	IsInactive	35
8.1.2.2	PlayerName	35
8.1.2.3	UserId	35
8.2	ExitGames.Client.Photon.Chat.AuthenticationValues Class Reference	36
8.2.1	Detailed Description	36
8.2.2	Constructor & Destructor Documentation	36
8.2.2.1	AuthenticationValues	36
8.2.2.2	AuthenticationValues	37
8.2.3	Member Function Documentation	38
8.2.3.1	AddAuthParameter	38
8.2.3.2	SetAuthPostData	38
8.2.3.3	SetAuthPostData	38
8.2.3.4	ToString	38
8.2.4	Property Documentation	38
8.2.4.1	AuthGetParameters	38
8.2.4.2	AuthPostData	38
8.2.4.3	AuthType	38
8.2.4.4	Token	39
8.2.4.5	UserId	39
8.3	AuthenticationValues Class Reference	39
8.3.1	Detailed Description	39
8.3.2	Constructor & Destructor Documentation	40
8.3.2.1	AuthenticationValues	40
8.3.2.2	AuthenticationValues	40

8.3.3	Member Function Documentation	40
8.3.3.1	AddAuthParameter	40
8.3.3.2	SetAuthPostData	40
8.3.3.3	SetAuthPostData	40
8.3.3.4	ToString	40
8.3.4	Property Documentation	41
8.3.4.1	AuthGetParameters	41
8.3.4.2	AuthPostData	41
8.3.4.3	AuthType	41
8.3.4.4	Token	41
8.3.4.5	UserId	41
8.4	ExitGames.Client.Photon.Chat.ChatChannel Class Reference	41
8.4.1	Detailed Description	42
8.4.2	Constructor & Destructor Documentation	42
8.4.2.1	ChatChannel	42
8.4.3	Member Function Documentation	42
8.4.3.1	Add	42
8.4.3.2	Add	42
8.4.3.3	ClearMessages	42
8.4.3.4	ToStringMessages	43
8.4.3.5	TruncateMessages	43
8.4.4	Member Data Documentation	43
8.4.4.1	MessageLimit	43
8.4.4.2	Messages	43
8.4.4.3	Name	43
8.4.4.4	Senders	43
8.4.5	Property Documentation	43
8.4.5.1	IsPrivate	43
8.4.5.2	MessageCount	43
8.5	ExitGames.Client.Photon.Chat.ChatClient Class Reference	43
8.5.1	Detailed Description	45
8.5.2	Constructor & Destructor Documentation	45
8.5.2.1	ChatClient	45
8.5.3	Member Function Documentation	45
8.5.3.1	AddFriends	45
8.5.3.2	CanChatInChannel	46
8.5.3.3	Connect	46
8.5.3.4	Disconnect	46
8.5.3.5	GetPrivateChannelNameByUser	46
8.5.3.6	PublishMessage	46

8.5.3.7	RemoveFriends	47
8.5.3.8	SendAcksOnly	47
8.5.3.9	SendPrivateMessage	47
8.5.3.10	SendPrivateMessage	48
8.5.3.11	Service	48
8.5.3.12	SetOnlineStatus	48
8.5.3.13	SetOnlineStatus	49
8.5.3.14	StopThread	49
8.5.3.15	Subscribe	49
8.5.3.16	Subscribe	49
8.5.3.17	TryGetChannel	49
8.5.3.18	TryGetChannel	50
8.5.3.19	Unsubscribe	50
8.5.4	Member Data Documentation	50
8.5.4.1	chatPeer	50
8.5.4.2	MessageLimit	50
8.5.4.3	PrivateChannels	51
8.5.4.4	PublicChannels	51
8.5.5	Property Documentation	51
8.5.5.1	AppId	51
8.5.5.2	AppVersion	51
8.5.5.3	AuthValues	51
8.5.5.4	CanChat	51
8.5.5.5	ChatRegion	51
8.5.5.6	DebugOut	51
8.5.5.7	DisconnectedCause	51
8.5.5.8	FrontendAddress	51
8.5.5.9	NameServerAddress	51
8.5.5.10	State	51
8.5.5.11	UserId	51
8.6	ExitGames.Client.Photon.Chat.ChatEventCode Class Reference	52
8.6.1	Detailed Description	52
8.6.2	Member Data Documentation	52
8.6.2.1	ChatMessages	52
8.6.2.2	FriendsList	52
8.6.2.3	PrivateMessage	52
8.6.2.4	StatusUpdate	52
8.6.2.5	Subscribe	52
8.6.2.6	Unsubscribe	52
8.6.2.7	Users	52

8.7	ExitGames.Client.Photon.Chat.ChatOperationCode Class Reference	52
8.7.1	Detailed Description	53
8.7.2	Member Data Documentation	53
8.7.2.1	AddFriends	53
8.7.2.2	Authenticate	53
8.7.2.3	ChannelHistory	53
8.7.2.4	Publish	53
8.7.2.5	RemoveFriends	53
8.7.2.6	SendPrivate	53
8.7.2.7	Subscribe	53
8.7.2.8	Unsubscribe	53
8.7.2.9	UpdateStatus	53
8.8	ExitGames.Client.Photon.Chat.ChatParameterCode Class Reference	54
8.8.1	Detailed Description	54
8.8.2	Member Data Documentation	55
8.8.2.1	Channel	55
8.8.2.2	Channels	55
8.8.2.3	ChannelUserCount	55
8.8.2.4	Friends	55
8.8.2.5	HistoryLength	55
8.8.2.6	Message	55
8.8.2.7	Messages	55
8.8.2.8	MsgId	55
8.8.2.9	MsgIds	55
8.8.2.10	Secret	55
8.8.2.11	Sender	55
8.8.2.12	Senders	56
8.8.2.13	SkipMessage	56
8.8.2.14	Status	56
8.8.2.15	SubscribeResults	56
8.8.2.16	UserId	56
8.8.2.17	WebFlags	56
8.9	ExitGames.Client.Photon.Chat.ChatPeer Class Reference	56
8.9.1	Detailed Description	57
8.9.2	Constructor & Destructor Documentation	57
8.9.2.1	ChatPeer	57
8.9.3	Member Function Documentation	57
8.9.3.1	AuthenticateOnNameServer	57
8.9.3.2	Connect	57
8.9.4	Member Data Documentation	57

8.9.4.1	NameServerHost	57
8.9.4.2	NameServerHttp	57
8.9.5	Property Documentation	57
8.9.5.1	NameServerAddress	57
8.10	ExitGames.Client.Photon.Chat.ChatUserStatus Class Reference	57
8.10.1	Detailed Description	58
8.10.2	Member Data Documentation	58
8.10.2.1	Away	58
8.10.2.2	DND	58
8.10.2.3	Invisible	58
8.10.2.4	LFG	58
8.10.2.5	Offline	58
8.10.2.6	Online	58
8.10.2.7	Playing	58
8.11	EncryptionDataParameters Class Reference	58
8.11.1	Member Data Documentation	59
8.11.1.1	Mode	59
8.11.1.2	Secret1	59
8.11.1.3	Secret2	59
8.12	ExitGames.Client.Photon.Chat.ErrorCode Class Reference	59
8.12.1	Detailed Description	60
8.12.2	Member Data Documentation	60
8.12.2.1	CustomAuthenticationFailed	60
8.12.2.2	GameClosed	60
8.12.2.3	GameDoesNotExist	60
8.12.2.4	GameFull	60
8.12.2.5	GameIdAlreadyExists	60
8.12.2.6	InternalServerError	60
8.12.2.7	InvalidAuthentication	60
8.12.2.8	InvalidOperationCode	60
8.12.2.9	InvalidRegion	61
8.12.2.10	MaxCcuReached	61
8.12.2.11	NoRandomMatchFound	61
8.12.2.12	Ok	61
8.12.2.13	OperationNotAllowedInCurrentState	61
8.12.2.14	ServerFull	61
8.12.2.15	UserBlocked	61
8.13	ErrorCode Class Reference	61
8.13.1	Detailed Description	63
8.13.2	Member Data Documentation	63

8.13.2.1	AlreadyMatched	63
8.13.2.2	AuthenticationTicketExpired	63
8.13.2.3	CustomAuthenticationFailed	63
8.13.2.4	ExternalHttpCallFailed	63
8.13.2.5	GameClosed	63
8.13.2.6	GameDoesNotExist	63
8.13.2.7	GameFull	64
8.13.2.8	GameIdAlreadyExists	64
8.13.2.9	HttpLimitReached	64
8.13.2.10	InternalServerError	64
8.13.2.11	InvalidAuthentication	64
8.13.2.12	InvalidEncryptionParameters	64
8.13.2.13	InvalidOperation	64
8.13.2.14	InvalidOperationCode	64
8.13.2.15	InvalidRegion	64
8.13.2.16	JoinFailedFoundActiveJoiner	65
8.13.2.17	JoinFailedFoundExcludedUserId	65
8.13.2.18	JoinFailedFoundInactiveJoiner	65
8.13.2.19	JoinFailedPeerAlreadyJoined	65
8.13.2.20	JoinFailedWithRejoinerNotFound	65
8.13.2.21	MaxCcuReached	65
8.13.2.22	NoRandomMatchFound	65
8.13.2.23	Ok	65
8.13.2.24	OperationNotAllowedInCurrentState	65
8.13.2.25	PluginMismatch	66
8.13.2.26	PluginReportedError	66
8.13.2.27	ServerFull	66
8.13.2.28	SlotError	66
8.13.2.29	UserBlocked	66
8.14	EventCode Class Reference	66
8.14.1	Detailed Description	67
8.14.2	Member Data Documentation	67
8.14.2.1	AppStats	67
8.14.2.2	AuthEvent	67
8.14.2.3	AzureNodeInfo	67
8.14.2.4	CacheSliceChanged	67
8.14.2.5	ErrorInfo	67
8.14.2.6	GameList	67
8.14.2.7	GameListUpdate	68
8.14.2.8	Join	68

8.14.2.9	Leave	68
8.14.2.10	LobbyStats	68
8.14.2.11	Match	68
8.14.2.12	PropertiesChanged	68
8.14.2.13	QueueState	68
8.14.2.14	SetProperties	68
8.15	Extensions Class Reference	68
8.15.1	Detailed Description	69
8.15.2	Member Function Documentation	69
8.15.2.1	AlmostEquals	69
8.15.2.2	AlmostEquals	69
8.15.2.3	AlmostEquals	69
8.15.2.4	AlmostEquals	69
8.15.2.5	Contains	70
8.15.2.6	GetCachedParameters	71
8.15.2.7	GetPhotonView	71
8.15.2.8	GetPhotonViewsInChildren	71
8.15.2.9	Merge	71
8.15.2.10	MergeStringKeys	71
8.15.2.11	StripKeysWithNullValues	71
8.15.2.12	StripToStringKeys	71
8.15.2.13	ToStringFull	72
8.15.2.14	ToStringFull	72
8.15.3	Member Data Documentation	72
8.15.3.1	ParametersOfMethods	72
8.16	FriendInfo Class Reference	72
8.16.1	Detailed Description	72
8.16.2	Member Function Documentation	73
8.16.2.1	ToString	73
8.16.3	Property Documentation	73
8.16.3.1	IsInRoom	73
8.16.3.2	IsOnline	73
8.16.3.3	Name	73
8.16.3.4	Room	73
8.17	GameObjectExtensions Class Reference	73
8.17.1	Detailed Description	73
8.17.2	Member Function Documentation	73
8.17.2.1	GetActive	73
8.18	GamePropertyKey Class Reference	73
8.18.1	Detailed Description	74

8.18.2	Member Data Documentation	74
8.18.2.1	CleanupCacheOnLeave	74
8.18.2.2	ExpectedUsers	74
8.18.2.3	IsOpen	74
8.18.2.4	IsVisible	74
8.18.2.5	MasterClientId	74
8.18.2.6	MaxPlayers	74
8.18.2.7	PlayerCount	74
8.18.2.8	PropsListedInLobby	75
8.18.2.9	Removed	75
8.19	ExitGames.Client.GUI.GizmoTypeDrawer Class Reference	75
8.19.1	Member Function Documentation	75
8.19.1.1	Draw	75
8.20	HelpURL Class Reference	75
8.20.1	Detailed Description	75
8.20.2	Constructor & Destructor Documentation	75
8.20.2.1	HelpURL	75
8.21	ExitGames.Client.Photon.Chat.IChatClientListener Interface Reference	75
8.21.1	Detailed Description	76
8.21.2	Member Function Documentation	76
8.21.2.1	DebugReturn	76
8.21.2.2	OnChatStateChange	76
8.21.2.3	OnConnected	76
8.21.2.4	OnDisconnected	76
8.21.2.5	OnGetMessages	77
8.21.2.6	OnPrivateMessage	77
8.21.2.7	OnStatusUpdate	77
8.21.2.8	OnSubscribed	77
8.21.2.9	OnUnsubscribed	77
8.22	IPunCallbacks Interface Reference	79
8.22.1	Detailed Description	80
8.22.2	Member Function Documentation	80
8.22.2.1	OnConnectedToMaster	80
8.22.2.2	OnConnectedToPhoton	81
8.22.2.3	OnConnectionFail	81
8.22.2.4	OnCreatedRoom	81
8.22.2.5	OnCustomAuthenticationFailed	81
8.22.2.6	OnCustomAuthenticationResponse	81
8.22.2.7	OnDisconnectedFromPhoton	82
8.22.2.8	OnFailedToConnectToPhoton	82

8.22.2.9	OnJoinedLobby	82
8.22.2.10	OnJoinedRoom	82
8.22.2.11	OnLeftLobby	82
8.22.2.12	OnLeftRoom	83
8.22.2.13	OnLobbyStatisticsUpdate	83
8.22.2.14	OnMasterClientSwitched	83
8.22.2.15	OnOwnershipRequest	83
8.22.2.16	OnOwnershipTransferred	83
8.22.2.17	OnPhotonCreateRoomFailed	83
8.22.2.18	OnPhotonCustomRoomPropertiesChanged	85
8.22.2.19	OnPhotonInstantiate	85
8.22.2.20	OnPhotonJoinRoomFailed	85
8.22.2.21	OnPhotonMaxCccuReached	85
8.22.2.22	OnPhotonPlayerActivityChanged	85
8.22.2.23	OnPhotonPlayerConnected	86
8.22.2.24	OnPhotonPlayerDisconnected	86
8.22.2.25	OnPhotonPlayerPropertiesChanged	86
8.22.2.26	OnPhotonRandomJoinFailed	86
8.22.2.27	OnReceivedRoomListUpdate	87
8.22.2.28	OnUpdatedFriendList	87
8.22.2.29	OnWebRpcResponse	87
8.23	IPunObservable Interface Reference	87
8.23.1	Detailed Description	88
8.24	IPunPrefabPool Interface Reference	88
8.24.1	Detailed Description	88
8.24.2	Member Function Documentation	88
8.24.2.1	Destroy	88
8.24.2.2	Instantiate	88
8.25	Photon.MonoBehaviour Class Reference	89
8.25.1	Detailed Description	89
8.25.2	Property Documentation	89
8.25.2.1	networkView	89
8.25.2.2	photonView	89
8.26	OperationCode Class Reference	89
8.26.1	Detailed Description	90
8.26.2	Member Data Documentation	90
8.26.2.1	Authenticate	90
8.26.2.2	AuthenticateOnce	91
8.26.2.3	ChangeGroups	91
8.26.2.4	CreateGame	91

8.26.2.5	ExchangeKeysForEncryption	91
8.26.2.6	FindFriends	91
8.26.2.7	GetGameList	91
8.26.2.8	GetLobbyStats	91
8.26.2.9	GetProperties	91
8.26.2.10	GetRegions	91
8.26.2.11	Join	91
8.26.2.12	JoinGame	91
8.26.2.13	JoinLobby	91
8.26.2.14	JoinRandomGame	91
8.26.2.15	Leave	92
8.26.2.16	LeaveLobby	92
8.26.2.17	RaiseEvent	92
8.26.2.18	ServerSettings	92
8.26.2.19	SetProperties	92
8.26.2.20	WebRpc	92
8.27	ExitGames.Client.Photon.Chat.ParameterCode Class Reference	92
8.27.1	Member Data Documentation	93
8.27.1.1	Address	93
8.27.1.2	ApplicationId	93
8.27.1.3	AppVersion	93
8.27.1.4	ClientAuthenticationData	93
8.27.1.5	ClientAuthenticationParams	93
8.27.1.6	ClientAuthenticationType	93
8.27.1.7	Region	93
8.27.1.8	Secret	93
8.27.1.9	UserId	93
8.28	ParameterCode Class Reference	93
8.28.1	Detailed Description	96
8.28.2	Member Data Documentation	97
8.28.2.1	ActorList	97
8.28.2.2	ActorNr	97
8.28.2.3	Add	97
8.28.2.4	Address	97
8.28.2.5	ApplicationId	97
8.28.2.6	AppVersion	97
8.28.2.7	AzureLocalNodeId	97
8.28.2.8	AzureMasterNodeId	97
8.28.2.9	AzureNodeInfo	97
8.28.2.10	Broadcast	97

8.28.2.11 Cache	97
8.28.2.12 CacheSliceIndex	97
8.28.2.13 CheckUserOnJoin	98
8.28.2.14 CleanupCacheOnLeave	98
8.28.2.15 ClientAuthenticationData	98
8.28.2.16 ClientAuthenticationParams	98
8.28.2.17 ClientAuthenticationType	98
8.28.2.18 Code	98
8.28.2.19 CustomEventContent	98
8.28.2.20 CustomInitData	98
8.28.2.21 Data	98
8.28.2.22 EmptyRoomTTL	98
8.28.2.23 EncryptionData	98
8.28.2.24 EncryptionMode	99
8.28.2.25 EventForward	99
8.28.2.26 ExpectedProtocol	99
8.28.2.27 ExpectedValues	99
8.28.2.28 FindFriendsRequestList	99
8.28.2.29 FindFriendsResponseOnlineList	99
8.28.2.30 FindFriendsResponseRoomIdList	99
8.28.2.31 GameCount	99
8.28.2.32 GameList	99
8.28.2.33 GameProperties	99
8.28.2.34 Group	99
8.28.2.35 Info	99
8.28.2.36 IsComingBack	100
8.28.2.37 IsInactive	100
8.28.2.38 JoinMode	100
8.28.2.39 LobbyName	100
8.28.2.40 LobbyStats	100
8.28.2.41 LobbyType	100
8.28.2.42 MasterClientId	100
8.28.2.43 MasterPeerCount	100
8.28.2.44 MatchMakingType	100
8.28.2.45 NickName	100
8.28.2.46 PeerCount	101
8.28.2.47 PlayerProperties	101
8.28.2.48 PlayerTTL	101
8.28.2.49 PluginName	101
8.28.2.50 Plugins	101

8.28.2.51 PluginVersion	101
8.28.2.52 Position	101
8.28.2.53 Properties	101
8.28.2.54 PublishUserId	101
8.28.2.55 ReceiverGroup	101
8.28.2.56 Region	101
8.28.2.57 Remove	102
8.28.2.58 RoomName	102
8.28.2.59 RoomOptionFlags	102
8.28.2.60 Secret	102
8.28.2.61 SuppressRoomEvents	102
8.28.2.62 TargetActorNr	102
8.28.2.63 UriPath	102
8.28.2.64 UserId	102
8.28.2.65 WebRpcParameters	102
8.28.2.66 WebRpcReturnCode	102
8.28.2.67 WebRpcReturnMessage	102
8.29 PhotonAnimatorView Class Reference	103
8.29.1 Detailed Description	103
8.29.2 Member Enumeration Documentation	104
8.29.2.1 ParameterType	104
8.29.2.2 SynchronizeType	104
8.29.3 Member Function Documentation	104
8.29.3.1 CacheDiscreteTriggers	104
8.29.3.2 DoesLayerSynchronizeTypeExist	104
8.29.3.3 DoesParameterSynchronizeTypeExist	104
8.29.3.4 GetLayerSynchronizeType	104
8.29.3.5 GetParameterSynchronizeType	105
8.29.3.6 GetSynchronizedLayers	105
8.29.3.7 GetSynchronizedParameters	105
8.29.3.8 OnPhotonSerializeView	105
8.29.3.9 SetLayerSynchronized	106
8.29.3.10 SetParameterSynchronized	106
8.30 PhotonLagSimulationGui Class Reference	106
8.30.1 Detailed Description	107
8.30.2 Member Function Documentation	107
8.30.2.1 OnGUI	107
8.30.2.2 Start	107
8.30.3 Member Data Documentation	107
8.30.3.1 Visible	107

8.30.3.2	WindowId	107
8.30.3.3	WindowRect	107
8.30.4	Property Documentation	107
8.30.4.1	Peer	107
8.31	PhotonMessageInfo Struct Reference	107
8.31.1	Detailed Description	108
8.31.2	Constructor & Destructor Documentation	108
8.31.2.1	PhotonMessageInfo	108
8.31.3	Member Function Documentation	108
8.31.3.1	ToString	108
8.31.4	Member Data Documentation	108
8.31.4.1	photonView	108
8.31.4.2	sender	108
8.31.5	Property Documentation	108
8.31.5.1	timestamp	108
8.32	PhotonNetwork Class Reference	108
8.32.1	Detailed Description	114
8.32.2	Member Function Documentation	114
8.32.2.1	AllocateSceneViewID	114
8.32.2.2	AllocateViewID	114
8.32.2.3	CacheSendMonoMessageTargets	114
8.32.2.4	CloseConnection	115
8.32.2.5	ConnectToBestCloudServer	115
8.32.2.6	ConnectToMaster	115
8.32.2.7	ConnectToRegion	116
8.32.2.8	ConnectUsingSettings	116
8.32.2.9	CreateRoom	116
8.32.2.10	CreateRoom	117
8.32.2.11	CreateRoom	117
8.32.2.12	Destroy	118
8.32.2.13	Destroy	119
8.32.2.14	DestroyAll	119
8.32.2.15	DestroyPlayerObjects	119
8.32.2.16	DestroyPlayerObjects	120
8.32.2.17	Disconnect	120
8.32.2.18	EventCallback	120
8.32.2.19	FetchServerTimestamp	120
8.32.2.20	FindFriends	121
8.32.2.21	FindGameObjectsWithComponent	121
8.32.2.22	GetCustomRoomList	121

8.32.2.23 GetPing	122
8.32.2.24 GetRoomList	122
8.32.2.25 InitializeSecurity	122
8.32.2.26 Instantiate	122
8.32.2.27 Instantiate	122
8.32.2.28 InstantiateSceneObject	123
8.32.2.29 JoinLobby	123
8.32.2.30 JoinLobby	123
8.32.2.31 JoinOrCreateRoom	124
8.32.2.32 JoinOrCreateRoom	124
8.32.2.33 JoinRandomRoom	125
8.32.2.34 JoinRandomRoom	125
8.32.2.35 JoinRandomRoom	126
8.32.2.36 JoinRoom	126
8.32.2.37 JoinRoom	127
8.32.2.38 LeaveLobby	127
8.32.2.39 LeaveRoom	127
8.32.2.40 LoadLevel	127
8.32.2.41 LoadLevel	128
8.32.2.42 NetworkStatisticsReset	128
8.32.2.43 NetworkStatisticsToString	128
8.32.2.44 OverrideBestCloudServer	128
8.32.2.45 RaiseEvent	128
8.32.2.46 Reconnect	129
8.32.2.47 ReconnectAndRejoin	129
8.32.2.48 RefreshCloudServerRating	129
8.32.2.49 ReJoinRoom	129
8.32.2.50 RemovePlayerCustomProperties	130
8.32.2.51 RemoveRPCs	130
8.32.2.52 RemoveRPCs	130
8.32.2.53 RemoveRPCsInGroup	131
8.32.2.54 SendOutgoingCommands	131
8.32.2.55 SetInterestGroups	131
8.32.2.56 SetInterestGroups	131
8.32.2.57 SetLevelPrefix	132
8.32.2.58 SetMasterClient	132
8.32.2.59 SetPlayerCustomProperties	133
8.32.2.60 SetReceivingEnabled	133
8.32.2.61 SetReceivingEnabled	133
8.32.2.62 SetSendingEnabled	133

8.32.2.63 SetSendingEnabled	133
8.32.2.64 SetSendingEnabled	133
8.32.2.65 SetSendingEnabled	133
8.32.2.66 SwitchToProtocol	133
8.32.2.67 UnAllocateViewID	134
8.32.2.68 WebRpc	134
8.32.3 Member Data Documentation	134
8.32.3.1 BackgroundTimeout	135
8.32.3.2 InstantiateInRoomOnly	135
8.32.3.3 logLevel	135
8.32.3.4 MAX_VIEW_IDS	135
8.32.3.5 maxConnections	135
8.32.3.6 OnEventCall	135
8.32.3.7 PhotonServerSettings	135
8.32.3.8 precisionForFloatSynchronization	136
8.32.3.9 precisionForQuaternionSynchronization	136
8.32.3.10 precisionForVectorSynchronization	136
8.32.3.11 PrefabCache	136
8.32.3.12 SendMonoMessageTargets	136
8.32.3.13 SendMonoMessageTargetType	136
8.32.3.14 StartRpcsAsCoroutine	136
8.32.3.15 UsePrefabCache	136
8.32.3.16 UseRpcMonoBehaviourCache	137
8.32.3.17 versionPUN	137
8.32.4 Property Documentation	137
8.32.4.1 AuthValues	137
8.32.4.2 autoCleanUpPlayerObjects	137
8.32.4.3 autoJoinLobby	137
8.32.4.4 automaticallySyncScene	138
8.32.4.5 CloudRegion	138
8.32.4.6 connected	138
8.32.4.7 connectedAndReady	138
8.32.4.8 connecting	138
8.32.4.9 connectionState	138
8.32.4.10 connectionStateDetailed	138
8.32.4.11 countOfPlayers	138
8.32.4.12 countOfPlayersInRooms	138
8.32.4.13 countOfPlayersOnMaster	138
8.32.4.14 countOfRooms	139
8.32.4.15 CrcCheckEnabled	139

8.32.4.16 EnableLobbyStatistics	139
8.32.4.17 Friends	139
8.32.4.18 FriendsListAge	139
8.32.4.19 gameVersion	139
8.32.4.20 inRoom	139
8.32.4.21 insideLobby	139
8.32.4.22 isMasterClient	140
8.32.4.23 isMessageQueueRunning	140
8.32.4.24 isNonMasterClientInRoom	140
8.32.4.25 lobby	140
8.32.4.26 LobbyStatistics	140
8.32.4.27 masterClient	140
8.32.4.28 MaxResendsBeforeDisconnect	141
8.32.4.29 NetworkStatisticsEnabled	141
8.32.4.30 offlineMode	141
8.32.4.31 otherPlayers	141
8.32.4.32 PacketLossByCrcCheck	141
8.32.4.33 player	141
8.32.4.34 playerList	141
8.32.4.35 playerName	141
8.32.4.36 PrefabPool	142
8.32.4.37 QuickResends	142
8.32.4.38 ResentReliableCommands	142
8.32.4.39 room	142
8.32.4.40 sendRate	142
8.32.4.41 sendRateOnSerialize	142
8.32.4.42 Server	142
8.32.4.43 ServerAddress	143
8.32.4.44 ServerTimestamp	143
8.32.4.45 time	143
8.32.4.46 unreliableCommandsLimit	143
8.33 PhotonPingManager Class Reference	143
8.33.1 Member Function Documentation	144
8.33.1.1 PingSocket	144
8.33.1.2 ResolveHost	144
8.33.2 Member Data Documentation	144
8.33.2.1 Attempts	144
8.33.2.2 IgnoreInitialAttempt	144
8.33.2.3 MaxMillisecondsPerPing	144
8.33.2.4 UseNative	144

8.33.3	Property Documentation	144
8.33.3.1	BestRegion	144
8.33.3.2	Done	144
8.34	PhotonPlayer Class Reference	144
8.34.1	Detailed Description	146
8.34.2	Constructor & Destructor Documentation	146
8.34.2.1	PhotonPlayer	146
8.34.3	Member Function Documentation	146
8.34.3.1	CompareTo	146
8.34.3.2	CompareTo	146
8.34.3.3	Equals	146
8.34.3.4	Equals	146
8.34.3.5	Equals	146
8.34.3.6	Find	146
8.34.3.7	Get	146
8.34.3.8	GetHashCode	146
8.34.3.9	GetNext	146
8.34.3.10	GetNextFor	146
8.34.3.11	GetNextFor	147
8.34.3.12	SetCustomProperties	147
8.34.3.13	ToString	147
8.34.3.14	ToStringFull	147
8.34.4	Member Data Documentation	147
8.34.4.1	IsLocal	148
8.34.4.2	TagObject	148
8.34.5	Property Documentation	148
8.34.5.1	AllProperties	148
8.34.5.2	allProperties	148
8.34.5.3	CustomProperties	148
8.34.5.4	customProperties	148
8.34.5.5	ID	148
8.34.5.6	IsInactive	148
8.34.5.7	isInactive	148
8.34.5.8	isLocal	148
8.34.5.9	IsMasterClient	148
8.34.5.10	isMasterClient	148
8.34.5.11	name	148
8.34.5.12	NickName	149
8.34.5.13	UserId	149
8.34.5.14	userId	149

8.35 PhotonRigidbody2DView Class Reference	149
8.35.1 Detailed Description	149
8.35.2 Member Function Documentation	149
8.35.2.1 OnPhotonSerializeView	149
8.36 PhotonRigidbodyView Class Reference	150
8.36.1 Detailed Description	150
8.36.2 Member Function Documentation	150
8.36.2.1 OnPhotonSerializeView	150
8.37 PhotonStatsGui Class Reference	151
8.37.1 Detailed Description	151
8.37.2 Member Function Documentation	152
8.37.2.1 OnGUI	152
8.37.2.2 Start	152
8.37.2.3 TrafficStatsWindow	152
8.37.2.4 Update	152
8.37.3 Member Data Documentation	152
8.37.3.1 buttonsOn	152
8.37.3.2 healthStatsVisible	152
8.37.3.3 statsOn	152
8.37.3.4 statsRect	152
8.37.3.5 statsWindowOn	152
8.37.3.6 trafficStatsOn	152
8.37.3.7 WindowId	152
8.38 PhotonStream Class Reference	152
8.38.1 Detailed Description	153
8.38.2 Constructor & Destructor Documentation	154
8.38.2.1 PhotonStream	154
8.38.3 Member Function Documentation	154
8.38.3.1 PeekNext	154
8.38.3.2 ReceiveNext	154
8.38.3.3 SendNext	154
8.38.3.4 Serialize	154
8.38.3.5 Serialize	154
8.38.3.6 Serialize	154
8.38.3.7 Serialize	154
8.38.3.8 Serialize	154
8.38.3.9 Serialize	154
8.38.3.10 Serialize	155
8.38.3.11 Serialize	155
8.38.3.12 Serialize	155

8.38.3.13	Serialize	155
8.38.3.14	SetReadStream	155
8.38.3.15	ToArray	155
8.38.4	Property Documentation	155
8.38.4.1	Count	155
8.38.4.2	isReading	155
8.38.4.3	isWriting	155
8.39	PhotonStreamQueue Class Reference	155
8.39.1	Detailed Description	156
8.39.2	Constructor & Destructor Documentation	156
8.39.2.1	PhotonStreamQueue	156
8.39.3	Member Function Documentation	156
8.39.3.1	Deserialize	156
8.39.3.2	HasQueuedObjects	156
8.39.3.3	ReceiveNext	156
8.39.3.4	Reset	157
8.39.3.5	SendNext	157
8.39.3.6	Serialize	157
8.40	PhotonTransformView Class Reference	157
8.40.1	Detailed Description	157
8.40.2	Member Function Documentation	157
8.40.2.1	OnPhotonSerializeView	157
8.40.2.2	SetSynchronizedValues	158
8.41	PhotonTransformViewPositionControl Class Reference	158
8.41.1	Constructor & Destructor Documentation	158
8.41.1.1	PhotonTransformViewPositionControl	158
8.41.2	Member Function Documentation	159
8.41.2.1	GetExtrapolatedPositionOffset	159
8.41.2.2	GetNetworkPosition	159
8.41.2.3	OnPhotonSerializeView	159
8.41.2.4	SetSynchronizedValues	159
8.41.2.5	UpdatePosition	159
8.42	PhotonTransformViewPositionModel Class Reference	159
8.42.1	Member Enumeration Documentation	160
8.42.1.1	ExtrapolateOptions	160
8.42.1.2	InterpolateOptions	160
8.42.2	Member Data Documentation	160
8.42.2.1	DrawErrorGizmo	160
8.42.2.2	ExtrapolateIncludingRoundTripTime	160
8.42.2.3	ExtrapolateNumberOfStoredPositions	160

8.42.2.4	ExtrapolateOption	160
8.42.2.5	ExtrapolateSpeed	160
8.42.2.6	InterpolateLerpSpeed	160
8.42.2.7	InterpolateMoveTowardsAcceleration	161
8.42.2.8	InterpolateMoveTowardsDeceleration	161
8.42.2.9	InterpolateMoveTowardsSpeed	161
8.42.2.10	InterpolateOption	161
8.42.2.11	InterpolateSpeedCurve	161
8.42.2.12	SynchronizeEnabled	161
8.42.2.13	TeleportEnabled	161
8.42.2.14	TeleportIfDistanceGreaterThan	161
8.43	PhotonTransformViewRotationControl Class Reference	161
8.43.1	Constructor & Destructor Documentation	161
8.43.1.1	PhotonTransformViewRotationControl	161
8.43.2	Member Function Documentation	161
8.43.2.1	GetNetworkRotation	161
8.43.2.2	GetRotation	161
8.43.2.3	OnPhotonSerializeView	162
8.44	PhotonTransformViewRotationModel Class Reference	162
8.44.1	Member Enumeration Documentation	162
8.44.1.1	InterpolateOptions	162
8.44.2	Member Data Documentation	162
8.44.2.1	InterpolateLerpSpeed	162
8.44.2.2	InterpolateOption	162
8.44.2.3	InterpolateRotateTowardsSpeed	162
8.44.2.4	SynchronizeEnabled	162
8.45	PhotonTransformViewScaleControl Class Reference	162
8.45.1	Constructor & Destructor Documentation	162
8.45.1.1	PhotonTransformViewScaleControl	162
8.45.2	Member Function Documentation	163
8.45.2.1	GetNetworkScale	163
8.45.2.2	GetScale	163
8.45.2.3	OnPhotonSerializeView	163
8.46	PhotonTransformViewScaleModel Class Reference	163
8.46.1	Member Enumeration Documentation	163
8.46.1.1	InterpolateOptions	163
8.46.2	Member Data Documentation	163
8.46.2.1	InterpolateLerpSpeed	163
8.46.2.2	InterpolateMoveTowardsSpeed	163
8.46.2.3	InterpolateOption	163

8.46.2.4 SynchronizeEnabled	163
8.47 PhotonView Class Reference	163
8.47.1 Detailed Description	165
8.47.2 Member Function Documentation	165
8.47.2.1 DeserializeView	165
8.47.2.2 Find	165
8.47.2.3 Get	165
8.47.2.4 Get	165
8.47.2.5 OnMasterClientSwitched	165
8.47.2.6 RefreshRpcMonoBehaviourCache	165
8.47.2.7 RequestOwnership	166
8.47.2.8 RPC	166
8.47.2.9 RPC	166
8.47.2.10 RpcSecure	166
8.47.2.11 RpcSecure	167
8.47.2.12 SerializeView	167
8.47.2.13 ToString	167
8.47.2.14 TransferOwnership	167
8.47.2.15 TransferOwnership	167
8.47.3 Member Data Documentation	167
8.47.3.1 currentMasterID	167
8.47.3.2 group	167
8.47.3.3 instantiationId	168
8.47.3.4 ObservedComponents	168
8.47.3.5 onSerializeRigidBodyOption	168
8.47.3.6 onSerializeTransformOption	168
8.47.3.7 ownerId	168
8.47.3.8 ownershipTransfer	168
8.47.3.9 OwnershipWasTransferred	168
8.47.3.10 prefixBackup	168
8.47.3.11 synchronization	168
8.47.4 Property Documentation	168
8.47.4.1 CreatorActorNr	168
8.47.4.2 instantiationData	168
8.47.4.3 isMine	168
8.47.4.4 isOwnerActive	168
8.47.4.5 isSceneView	168
8.47.4.6 owner	169
8.47.4.7 OwnerActorNr	169
8.47.4.8 prefix	169

8.47.4.9	viewID	169
8.48	PingMonoEditor Class Reference	169
8.48.1	Detailed Description	169
8.48.2	Member Function Documentation	169
8.48.2.1	Dispose	169
8.48.2.2	Done	169
8.48.2.3	StartPing	169
8.49	Photon.PunBehaviour Class Reference	170
8.49.1	Detailed Description	171
8.49.2	Member Function Documentation	171
8.49.2.1	OnConnectedToMaster	171
8.49.2.2	OnConnectedToPhoton	172
8.49.2.3	OnConnectionFail	172
8.49.2.4	OnCreatedRoom	172
8.49.2.5	OnCustomAuthenticationFailed	172
8.49.2.6	OnCustomAuthenticationResponse	172
8.49.2.7	OnDisconnectedFromPhoton	173
8.49.2.8	OnFailedToConnectToPhoton	173
8.49.2.9	OnJoinedLobby	173
8.49.2.10	OnJoinedRoom	173
8.49.2.11	OnLeftLobby	173
8.49.2.12	OnLeftRoom	174
8.49.2.13	OnLobbyStatisticsUpdate	174
8.49.2.14	OnMasterClientSwitched	174
8.49.2.15	OnOwnershipRequest	174
8.49.2.16	OnOwnershipTransferred	174
8.49.2.17	OnPhotonCreateRoomFailed	175
8.49.2.18	OnPhotonCustomRoomPropertiesChanged	175
8.49.2.19	OnPhotonInstantiate	175
8.49.2.20	OnPhotonJoinRoomFailed	175
8.49.2.21	OnPhotonMaxCccuReached	175
8.49.2.22	OnPhotonPlayerActivityChanged	176
8.49.2.23	OnPhotonPlayerConnected	176
8.49.2.24	OnPhotonPlayerDisconnected	176
8.49.2.25	OnPhotonPlayerPropertiesChanged	176
8.49.2.26	OnPhotonRandomJoinFailed	176
8.49.2.27	OnReceivedRoomListUpdate	177
8.49.2.28	OnUpdatedFriendList	177
8.49.2.29	OnWebRpcResponse	177
8.50	PunRPC Class Reference	177

8.50.1 Detailed Description	177
8.51 RaiseEventOptions Class Reference	178
8.51.1 Detailed Description	178
8.51.2 Member Data Documentation	178
8.51.2.1 CachingOption	178
8.51.2.2 Default	178
8.51.2.3 Encrypt	178
8.51.2.4 ForwardToWebhook	178
8.51.2.5 InterestGroup	179
8.51.2.6 Receivers	179
8.51.2.7 SequenceChannel	179
8.51.2.8 TargetActors	179
8.52 Region Class Reference	179
8.52.1 Constructor & Destructor Documentation	179
8.52.1.1 Region	179
8.52.1.2 Region	179
8.52.2 Member Function Documentation	179
8.52.2.1 Parse	179
8.52.2.2 ToString	179
8.52.3 Member Data Documentation	180
8.52.3.1 Cluster	180
8.52.3.2 Code	180
8.52.3.3 HostAndPort	180
8.52.3.4 Ping	180
8.53 Room Class Reference	180
8.53.1 Detailed Description	181
8.53.2 Member Function Documentation	181
8.53.2.1 ClearExpectedUsers	181
8.53.2.2 SetCustomProperties	181
8.53.2.3 SetPropertiesListedInLobby	182
8.53.2.4 ToString	182
8.53.2.5 ToStringFull	182
8.53.3 Property Documentation	182
8.53.3.1 AutoCleanUp	182
8.53.3.2 autoCleanUp	183
8.53.3.3 ExpectedUsers	183
8.53.3.4 expectedUsers	183
8.53.3.5 IsOpen	183
8.53.3.6 IsVisible	183
8.53.3.7 MaxPlayers	183

8.53.3.8	maxPlayers	183
8.53.3.9	Name	183
8.53.3.10	name	183
8.53.3.11	open	183
8.53.3.12	PlayerCount	183
8.53.3.13	playerCount	183
8.53.3.14	PropertiesListedInLobby	183
8.53.3.15	propertiesListedInLobby	183
8.53.3.16	visible	183
8.54	RoomInfo Class Reference	184
8.54.1	Detailed Description	185
8.54.2	Member Function Documentation	185
8.54.2.1	Equals	185
8.54.2.2	GetHashCode	185
8.54.2.3	ToString	185
8.54.2.4	ToStringFull	185
8.54.3	Member Data Documentation	186
8.54.3.1	autoCleanUpField	186
8.54.3.2	expectedUsersField	186
8.54.3.3	maxPlayersField	186
8.54.3.4	nameField	186
8.54.3.5	openField	186
8.54.3.6	visibleField	186
8.54.4	Property Documentation	186
8.54.4.1	CustomProperties	186
8.54.4.2	customProperties	186
8.54.4.3	IsLocalClientInside	186
8.54.4.4	isLocalClientInside	186
8.54.4.5	IsOpen	186
8.54.4.6	IsVisible	187
8.54.4.7	MaxPlayers	187
8.54.4.8	maxPlayers	187
8.54.4.9	Name	187
8.54.4.10	name	187
8.54.4.11	open	187
8.54.4.12	PlayerCount	187
8.54.4.13	playerCount	187
8.54.4.14	removedFromList	187
8.54.4.15	visible	187
8.55	RoomOptions Class Reference	187

8.55.1 Detailed Description	188
8.55.2 Member Data Documentation	188
8.55.2.1 CustomRoomProperties	188
8.55.2.2 CustomRoomPropertiesForLobby	189
8.55.2.3 EmptyRoomTtl	189
8.55.2.4 MaxPlayers	189
8.55.2.5 PlayerTtl	189
8.55.2.6 Plugins	189
8.55.3 Property Documentation	189
8.55.3.1 CleanupCacheOnLeave	189
8.55.3.2 cleanupCacheOnLeave	189
8.55.3.3 customRoomProperties	189
8.55.3.4 customRoomPropertiesForLobby	189
8.55.3.5 DeleteNullProperties	189
8.55.3.6 IsOpen	190
8.55.3.7 isOpen	190
8.55.3.8 IsVisible	190
8.55.3.9 isVisible	190
8.55.3.10 maxPlayers	190
8.55.3.11 plugins	190
8.55.3.12 PublishUserId	190
8.55.3.13 publishUserId	190
8.55.3.14 SuppressRoomEvents	190
8.55.3.15 suppressRoomEvents	190
8.56 UnityEngine.SceneManagement.SceneManager Class Reference	190
8.56.1 Detailed Description	191
8.56.2 Member Function Documentation	191
8.56.2.1 LoadScene	191
8.56.2.2 LoadScene	191
8.57 SceneManagerHelper Class Reference	191
8.57.1 Property Documentation	191
8.57.1.1 ActiveSceneBuildIndex	191
8.57.1.2 ActiveSceneName	191
8.58 ServerSettings Class Reference	191
8.58.1 Detailed Description	192
8.58.2 Member Enumeration Documentation	192
8.58.2.1 HostingOption	192
8.58.3 Member Function Documentation	192
8.58.3.1 IsAppld	192
8.58.3.2 ResetBestRegionCodeInPreferences	193

8.58.3.3	ToString	193
8.58.3.4	UseCloud	193
8.58.3.5	UseCloud	193
8.58.3.6	UseCloudBestRegion	193
8.58.3.7	UseMyServer	193
8.58.4	Member Data Documentation	193
8.58.4.1	AppID	193
8.58.4.2	ChatAppID	193
8.58.4.3	DisableAutoOpenWizard	193
8.58.4.4	EnabledRegions	193
8.58.4.5	EnableLobbyStatistics	193
8.58.4.6	HostType	193
8.58.4.7	JoinLobby	193
8.58.4.8	NetworkLogging	193
8.58.4.9	PreferredRegion	193
8.58.4.10	Protocol	193
8.58.4.11	PunLogging	193
8.58.4.12	RpcList	193
8.58.4.13	RunInBackground	193
8.58.4.14	ServerAddress	193
8.58.4.15	ServerPort	193
8.58.4.16	VoiceAppID	193
8.58.4.17	VoiceServerPort	193
8.58.5	Property Documentation	194
8.58.5.1	BestRegionCodeInPreferences	194
8.59	PhotonAnimatorView.SynchronizedLayer Class Reference	194
8.59.1	Member Data Documentation	194
8.59.1.1	LayerIndex	194
8.59.1.2	SynchronizeType	194
8.60	PhotonAnimatorView.SynchronizedParameter Class Reference	194
8.60.1	Member Data Documentation	194
8.60.1.1	Name	194
8.60.1.2	SynchronizeType	194
8.60.1.3	Type	194
8.61	TypedLobby Class Reference	194
8.61.1	Detailed Description	195
8.61.2	Constructor & Destructor Documentation	195
8.61.2.1	TypedLobby	195
8.61.2.2	TypedLobby	195
8.61.3	Member Function Documentation	195

8.61.3.1	ToString	195
8.61.4	Member Data Documentation	195
8.61.4.1	Default	195
8.61.4.2	Name	195
8.61.4.3	Type	195
8.61.5	Property Documentation	195
8.61.5.1	IsDefault	195
8.62	TypedLobbyInfo Class Reference	196
8.62.1	Member Function Documentation	196
8.62.1.1	ToString	196
8.62.2	Member Data Documentation	196
8.62.2.1	PlayerCount	196
8.62.2.2	RoomCount	196
8.63	WebRpcResponse Class Reference	196
8.63.1	Detailed Description	197
8.63.2	Constructor & Destructor Documentation	197
8.63.2.1	WebRpcResponse	197
8.63.3	Member Function Documentation	197
8.63.3.1	ToStringFull	197
8.63.4	Property Documentation	197
8.63.4.1	DebugMessage	197
8.63.4.2	Name	197
8.63.4.3	Parameters	197
8.63.4.4	ReturnCode	197
9	File Documentation	199
9.1	C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking/Assets/_Doc/general.md File Reference	199
9.2	C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking/Assets/_Doc/main.md File Reference	199
9.3	C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking/Assets/_Doc/optionalGui.md File Reference	199
9.4	C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking/Assets/_Doc/photonStatsGui.md File Reference	199
9.5	C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking/Assets/_Doc/publicApi.md File Reference	199
9.6	C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking/Assets/Photon Unity Networking/Plugins/PhotonNetwork/CustomTypes.cs File Reference	199
9.6.1	Detailed Description	199
9.7	C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking/Assets/Photon Unity Networking/Plugins/PhotonNetwork/Enums.cs File Reference	200
9.7.1	Detailed Description	201
9.7.2	Enumeration Type Documentation	201
9.7.2.1	CloudRegionCode	201
9.7.2.2	CloudRegionFlag	201
9.7.2.3	ConnectionState	202

9.7.2.4	EncryptionMode	202
9.8	C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking/Assets/Photon Unity Networking/Plugins/↔ PhotonNetwork/Extensions.cs File Reference	202
9.8.1	Typedef Documentation	202
9.8.1.1	Hashtable	202
9.8.1.2	SupportClassPun	202
9.9	C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking/Assets/Photon Unity Networking/Plugins/↔ PhotonNetwork/FriendInfo.cs File Reference	202
9.10	C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking/Assets/Photon Unity Networking/Plugins/↔ PhotonNetwork/GizmoType.cs File Reference	203
9.11	C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking/Assets/Photon Unity Networking/Plugins/↔ PhotonNetwork/LoadbalancingPeer.cs File Reference	203
9.11.1	Enumeration Type Documentation	204
9.11.1.1	AuthModeOption	204
9.11.1.2	CustomAuthenticationType	205
9.11.1.3	EventCaching	205
9.11.1.4	JoinMode	205
9.11.1.5	LobbyType	206
9.11.1.6	MatchmakingMode	206
9.11.1.7	PropertyTypeFlag	206
9.11.1.8	ReceiverGroup	206
9.12	C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking/Assets/Photon Unity Networking/Plugins/↔ PhotonNetwork/NetworkingPeer.cs File Reference	207
9.12.1	Typedef Documentation	207
9.12.1.1	Hashtable	207
9.12.1.2	SupportClassPun	207
9.12.2	Enumeration Type Documentation	207
9.12.2.1	ServerConnection	208
9.13	C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking/Assets/Photon Unity Networking/Plugins/↔ PhotonNetwork/PhotonClasses.cs File Reference	208
9.13.1	Detailed Description	209
9.13.2	Typedef Documentation	209
9.13.2.1	Hashtable	209
9.13.2.2	SupportClassPun	209
9.14	C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking/Assets/Photon Unity Networking/Plugins/↔ PhotonNetwork/PhotonHandler.cs File Reference	209
9.14.1	Typedef Documentation	209
9.14.1.1	Debug	209
9.14.1.2	Hashtable	209
9.14.1.3	SupportClassPun	209
9.15	C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking/Assets/Photon Unity Networking/Plugins/↔ PhotonNetwork/PhotonLagSimulationGui.cs File Reference	209

9.15.1	Detailed Description			210
9.16	C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking/Assets/Photon	Unity	Networking/Plugins/↔	
	PhotonNetwork/PhotonNetwork.cs File Reference			210
9.16.1	Typedef Documentation			210
9.16.1.1	Debug			210
9.16.1.2	Hashtable			210
9.17	C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking/Assets/Photon	Unity	Networking/Plugins/↔	
	PhotonNetwork/PhotonPlayer.cs File Reference			210
9.17.1	Typedef Documentation			210
9.17.1.1	Hashtable			210
9.18	C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking/Assets/Photon	Unity	Networking/Plugins/↔	
	PhotonNetwork/PhotonStatsGui.cs File Reference			210
9.18.1	Detailed Description			211
9.19	C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking/Assets/Photon	Unity	Networking/Plugins/↔	
	PhotonNetwork/PhotonStreamQueue.cs File Reference			211
9.20	C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking/Assets/Photon	Unity	Networking/Plugins/↔	
	PhotonNetwork/PhotonView.cs File Reference			211
9.20.1	Enumeration Type Documentation			211
9.20.1.1	OnSerializeRigidBody			211
9.20.1.2	OnSerializeTransform			211
9.20.1.3	OwnershipOption			212
9.20.1.4	ViewSynchronization			212
9.21	C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking/Assets/Photon	Unity	Networking/Plugins/↔	
	PhotonNetwork/PingCloudRegions.cs File Reference			212
9.21.1	Typedef Documentation			212
9.21.1.1	Debug			212
9.21.1.2	SupportClassPun			212
9.22	C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking/Assets/Photon	Unity	Networking/Plugins/↔	
	PhotonNetwork/Room.cs File Reference			213
9.23	C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking/Assets/Photon	Unity	Networking/Plugins/↔	
	PhotonNetwork/RoomInfo.cs File Reference			213
9.24	C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking/Assets/Photon	Unity	Networking/Plugins/↔	
	PhotonNetwork/RPC.cs File Reference			213
9.24.1	Detailed Description			213
9.25	C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking/Assets/Photon	Unity	Networking/Plugins/↔	
	PhotonNetwork/ServerSettings.cs File Reference			213
9.25.1	Detailed Description			213
9.26	C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking/Assets/Photon	Unity	Networking/Plugins/↔	
	PhotonNetwork/SocketWebTcp.cs File Reference			214
9.27	C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking/Assets/Photon	Unity	Networking/Plugins/↔	
	PhotonNetwork/Views/PhotonAnimatorView.cs File Reference			214
9.28	C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking/Assets/Photon	Unity	Networking/Plugins/↔	
	PhotonNetwork/Views/PhotonRigidbody2DView.cs File Reference			214

9.29	C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking/Assets/Photon Unity Networking/Plugins/↔ PhotonNetwork/Views/PhotonRigidbodyView.cs File Reference	214
9.30	C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking/Assets/Photon Unity Networking/Plugins/↔ PhotonNetwork/Views/PhotonTransformView.cs File Reference	214
9.31	C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking/Assets/Photon Unity Networking/Plugins/↔ PhotonNetwork/Views/PhotonTransformViewPositionControl.cs File Reference	215
9.32	C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking/Assets/Photon Unity Networking/Plugins/↔ PhotonNetwork/Views/PhotonTransformViewPositionModel.cs File Reference	215
9.33	C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking/Assets/Photon Unity Networking/Plugins/↔ PhotonNetwork/Views/PhotonTransformViewRotationControl.cs File Reference	215
9.34	C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking/Assets/Photon Unity Networking/Plugins/↔ PhotonNetwork/Views/PhotonTransformViewRotationModel.cs File Reference	215
9.35	C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking/Assets/Photon Unity Networking/Plugins/↔ PhotonNetwork/Views/PhotonTransformViewScaleControl.cs File Reference	215
9.36	C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking/Assets/Photon Unity Networking/Plugins/↔ PhotonNetwork/Views/PhotonTransformViewScaleModel.cs File Reference	215
9.37	C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking/Assets/PhotonChatApi/ChatChannel.cs File Reference	216
9.38	C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking/Assets/PhotonChatApi/ChatClient.cs File Refer- ence	216
9.39	C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking/Assets/PhotonChatApi/ChatDisconnect↔ Cause.cs File Reference	216
9.40	C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking/Assets/PhotonChatApi/ChatEventCode.cs File Reference	217
9.41	C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking/Assets/PhotonChatApi/ChatOperationCode.cs File Reference	217
9.42	C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking/Assets/PhotonChatApi/ChatParameterCode.cs File Reference	217
9.43	C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking/Assets/PhotonChatApi/ChatPeer.cs File Refer- ence	217
9.44	C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking/Assets/PhotonChatApi/ChatState.cs File Refer- ence	218
9.45	C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking/Assets/PhotonChatApi/ChatUserStatus.cs File Reference	218
9.46	C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking/Assets/PhotonChatApi/IChatClientListener.cs File Reference	219

Chapter 1

Main Page

Introduction

Photon is a real-time multiplayer game development framework that is fast, lean and flexible. **Photon** consists of a server and multiple client SDKs for major platforms.

Photon Unity Network (PUN) is our is our take on a Unity specific, high-level solution: Matchmaking, easy to use callbacks, components to synchronize GameObjects, Remote Procedure Calls (RPCs) and similar features provide a great start. Beyond that is a solid, extensive API for more advanced control.

Full source code is available, so you can scale this plugin to support any type of multiplayer game you come up with.

This plugin is compatible with the managed **Photon Cloud** service, which runs **Photon** Servers for you. A setup window registers you (for free) in less than a minute.

Most notable features:

- Dead-easy API
- Lots of demos and an extensive **PUN Basics Tutorial**
- Server available as hosted service (free for development) or as "On Premise"
- Load-balanced! Scales across servers (with no extra effort)
- Outstanding performance of the **Photon** Server
- Dedicated servers. No NAT punch-through needed
- Offline mode: re-use your multiplayer code in singleplayer game modes

First Steps

Import PUN into a new, empty project. Register via the pop up "wizard" (ALT+P) to get you a free **Photon** Cloud subscription (saving an initial Appld for you). Now you're ready to run and dissect the Demos.

Make sure to open and code the **PUN Basics Tutorial**.

General Documentation (API)

Continue reading the **General Documentation**.

Check out the growing doc pages online: <http://doc.photonengine.com/en-us/pun/current>

Chapter 2

General Documentation

Brief overview of Photon, subscriptions, hosting options and how to start.

2.1 Photon

Unlike Unity's built-in networking or Bolt, PUN always connects to a dedicated server which provides rooms, match-making and in-room communication for players. Behind the scenes [Photon](#) Unity Networking uses more than one server: Several "Game Servers" run the actual rooms (matches) while a "Master Server" keeps track of rooms and match players.

You have two options for the server side.

Exit Games Cloud

The Exit Games Cloud is a service which provides hosted and load balanced [Photon](#) Servers for you, fully managed by Exit Games. Free trials are available and [subscription costs for commercial use](#) are competitively low.

The service runs a fixed logic, so you can't implement your own server-side game logic. Instead, the clients need to be authoritative.

Clients are separated by "application id", which relates to your game title and a "game version". With that, your players won't clash with those of another developer or older game iterations.

Subscriptions bought in Asset Store

Follow these steps, if you bought a package with [Photon](#) Cloud Subscription in the Asset Store:

- Register a Photon Cloud Account: exitgames.com/en/Account/SignUp
- Create an App and get your AppID from the [Dashboard](#)
- Send a Mail to: developer@exitgames.com
- With:
 - Your Name and Company (if applicable)
 - Invoice/Purchase ID from the Asset Store
 - Photon Cloud AppID

Photon Server SDK

As alternative to the [Photon](#) Cloud service, you can run your own server and develop server side logic on top of our "Load Balancing" C# solution. This gives you full control of the server logic.

The Photon Server SDK can be downloaded on: www.exitgames.com/en/OnPremise/Download

Starting the Server: doc.exitgames.com/en/onpremise/current/getting-started/photon-server-in-5m

Photon Unity Networking - First steps

When you import PUN, the "Wizard" window will popup. Either enter your email address to register for the cloud, skip this step to enter the Appld of an existing account or switch to "self hosted" [Photon](#) to enter your server's address.

This creates a configuration for either the cloud service or your own [Photon](#) server in the project: PhotonServer↔ Settings.

PUN consists of quite a few files, however there's only one that truly matters: [PhotonNetwork](#). This class contains all functions and variables needed. If you ever have custom requirements, you can always modify the source files - this plugin is just an implementation of [Photon](#) after all.

To use PUN from UnityScript, move both folders "PhotonNetwork" and "UtilityScripts" to the Assets\ folder.

To show you how this API works, here are a few examples right away.

2.1.1 Master Server And Lobby

PUN always uses a master server and one or more game servers. The master server manages currently running games on the various game servers and will provide a game server address when you join or create a room. PUN (the client) automatically switches to that game server.

Individual matches are known as Rooms. They are independent of each other and identified by name. Rooms are grouped into one or multiple lobbies. Lobbies are an optional part in matchmaking. If you don't use custom lobbies explicitly, PUN will use a single lobby for all rooms.

By default, PUN will join the default lobby after connecting. This lobby sends a list of existing rooms to the client, so the player can pick a room (by name or some properties listed). Access the current list by using [PhotonNetwork](#).↔ [GetRoomList\(\)](#). The lists is updated in intervals to keep traffic low.

Clients don't have to join a lobby to join or create rooms. If you don't want to show a list of rooms in your client, set [PhotonNetwork.autoJoinLobby](#) = false before you connect and your clients will skip the lobby.

You can use more than one lobby to organize room-lists as needed for your game. [PhotonNetwork.JoinLobby](#) is the method to join a specific lobby. You can make them up on the client side - the server will keep track of them. As long as name and type are the same, the [TypedLobby](#) will be the same for all clients, too.

A client is always just in one lobby and while being in a lobby, creating a room will relate to this lobby, too. Multiple lobbies mean the clients get shorter rooms lists, which is good. There is no limit to the rooms lists.

A parameter in JoinRoom, JoinRandomRoom and CreateRoom enables you to select a lobby without joining it.

Players won't notice each other in the Lobby and can't send data (to prevent issues when it's getting crowded).

The servers are all run on dedicated machines - there is no such thing as player-hosted 'servers'. You don't have to bother remembering about the server organization though, as the API all hides this for you.

```
PhotonNetwork.ConnectUsingSettings("v1.0");
```

The code above is required to make use of any [PhotonNetwork](#) features. It sets your client's game version and uses the setup-wizard's config (stored in: PhotonServerSettings). The wizard can also be used when you host [Photon](#) yourself. Alternatively, use Connect() and you can ignore the PhotonServerSettings file.

Versioning

The [Photon](#) Cloud uses your appId to separate your players from everyone else's.

Within one AppId, you can deliberately separate clients/players by the "Game Version" string, which is set in the "connect" methods (as parameter).

Note: As we can't guarantee that different [Photon](#) Unity Networking versions are compatible with each other, we add the PUN version to your game's version. This literally adds "_" + [PhotonNetwork.versionPUN](#) to your Game Version string.

Creating and Joining Games

Next, you'll want to join or create a room. The following code showcases some required functions:

```
//Join a room
PhotonNetwork.JoinRoom(roomName);

//Create this room.
PhotonNetwork.CreateRoom(roomName);
// Fails if it already exists and calls: OnPhotonCreateGameFailed

//Tries to join any random game:
PhotonNetwork.JoinRandomRoom();
//Fails if there are no matching games: OnPhotonRandomJoinFailed
```

A list of currently running games is provided by the master server's lobby. It can be joined like other rooms but only provides and updates the list of rooms. The [PhotonNetwork](#) plugin will automatically join the lobby after connecting. When you're joining a room, the list will no longer update.

To display the list of rooms (in a lobby):

```
foreach (RoomInfo game in PhotonNetwork.GetRoomList())
{
    GUILayout.Label(game.name + " " + game.playerCount + "/" + game.maxPlayers);
}
```

Alternatively, the game can use random matchmaking: It will try to join any room and fail if none has room for another player. In that case: Create a room without name and wait until other players join it randomly.

Advanced Matchmaking & [Room](#) Properties

Fully random matchmaking is not always something players enjoy. Sometimes you just want to play a certain map or just two versus two.

In [Photon](#) Cloud and Loadbalancing, you can set arbitrary room properties and filter for those in JoinRandom.

[Room](#) Properties and the Lobby

[Room](#) properties are synced to all players in the room and can be useful to keep track of the current map, round, starttime, etc. They are handled as Hashtable with string keys. Preferably short keys.

You can forward selected properties to the lobby, too. This makes them available for listing them and for random matchmaking, too. Not all room properties are interesting in the lobby, so you define the set of properties for the lobby on room creation.

```
Hashtable roomProps = new Hashtable() { { "map", 1 } };
string[] roomPropsInLobby = { "map", "ai" };

RoomOptions roomOptions = new RoomOptions() { customRoomProperties = roomProps,
    customRoomPropertiesForLobby = roomPropsInLobby }
CreateRoom(roomName, roomOptions, TypedLobby.Default)
```

Note that "ai" is not a key in the room-properties yet. It won't show up in the lobby until it's set in the game via [Room.SetCustomProperties\(\)](#). When you change the values for "map" or "ai", they will be updated in the lobby with a short delay, too.

Keep the list short to make sure performance doesn't suffer from loading the list.

Filtering [Room](#) Properties in Join Random

In JoinRandom, you could pass a Hashtable with expected room properties and max player value. These work as filters when the server selects a "fitting" room for you.

```
Hashtable expectedCustomRoomProperties = new Hashtable() { { "map", 1 } };
JoinRandomRoom(expectedCustomRoomProperties, 4);
```

If you pass more filter properties, chances are lower that a room matches them. Better limit the options.

Make sure you never filter for properties that are not known to the lobby (see above).

MonoBehaviour Callbacks

PUN uses several callbacks to let your game know about state changes like "connected" or "joined a game". All you have to do is implement the fitting method in any MonoBehaviour and it gets called when the event happens.

To get a good overview of available callbacks, take a look at the class [Photon.PunBehaviour](#). If you make your script a [PunBehaviour](#) (instead of a MonoBehaviour), you can override individual callbacks easily. If you begin to type "override", your coding IDE should provide you a list of callbacks, so they are easy to find while coding, too.

This covers the basics of setting up game rooms. Next up is actual communication in games.

Sending messages in rooms

Inside a room you are able to send network messages to other connected players. Furthermore you are able to send buffered messages that will also be sent to players that connect in the future (for spawning your player for instance).

Sending messages can be done using two methods. Either RPCs or by using the [PhotonView](#) property [OnSerializePhotonView](#). There is more network interaction though. You can listen for callbacks for certain network events (e.g. [OnPhotonInstantiate](#), [OnPhotonPlayerConnected](#)) and you can trigger some of these events ([PhotonNetwork.Instantiate](#)). Don't worry if you're confused by the last paragraph, next up we'll explain for each of these subjects.

Using Groups in PUN

Groups are not synchronized when they are changed on any [PhotonView](#). It's up to the developer to keep photonviews in the same groups on all clients, if that's needed. Using different group numbers for the same photonview on several clients will cause some inconsistent behaviour.

Some network messages are checked for their receiver group at the receiver side only, namely:

- RPCS that are targeted to a single player (or MasterClient)
- RPCS that are buffered (AllBuffered/OthersBuffered).
- This includes [PhotonNetwork.Instantiate](#) (as it is buffered).

Technical reason for this: the photon server only supports interestgroups for messages that are not cached and are not targetted at sepcific actor(s). This might change in the future.

PhotonView

PhotonView is a script component that is used to send messages (RPCs and `OnSerializePhotonView`). You need to attach the **PhotonView** to your game's gameobjects. Note that the **PhotonView** is very similar to Unity's `NetworkView`.

At all times, you need at least one **PhotonView** in your game in order to send messages and optionally instantiate/allocate other PhotonViews.

To add a **PhotonView** to a gameobject, simply select a gameobject and use: "Components/Miscellaneous/Photon View".

Observe Transform

If you attach a Transform to a PhotonView's Observe property, you can choose to sync Position, Rotation and Scale or a combination of those across the players. This can be a great help for prototyping or smaller games. Note: A change to any observed value will send out all observed values - not just the single value that's changed. Also, updates are not smoothed or interpolated.

Observe MonoBehaviour

A **PhotonView** can be set to observe a MonoBehaviour. In this case, the script's `OnPhotonSerializeView` method will be called. This method is called for writing an object's state and for reading it, depending on whether the script is controlled by the local player.

The simple code below shows how to add character state synchronization with just a few lines of code more:

```
void OnPhotonSerializeView(PhotonStream stream,
    PhotonMessageInfo info)
{
    if (stream.isWriting)
    {
        //We own this player: send the others our data
        stream.SendNext((int)controllerScript._characterState);
        stream.SendNext(transform.position);
        stream.SendNext(transform.rotation);
    }
    else
    {
        //Network player, receive data
        controllerScript._characterState = (CharacterState)(int)stream.ReceiveNext();
        correctPlayerPos = (Vector3)stream.ReceiveNext();
        correctPlayerRot = (Quaternion)stream.ReceiveNext();
    }
}
```

If you send something "ReliableDeltaCompressed", make sure to always write data to the stream in the same order. If you write no data to the **PhotonStream**, the update is not sent. This can be useful in pauses. Now on, to yet another way to communicate: RPCs.

2.1.2 Remote Procedure Calls

Remote Procedure Calls (RPCs) are exactly what the name implies: methods that can be called on remote clients in the same room. To enable remote calls for a method of a MonoBehaviour, you must apply the attribute: **[PunRPC]**. A **PhotonView** instance is needed on the same GameObject, to call the marked functions.

```
[PunRPC]
void ChatMessage(string a, string b)
{
    Debug.Log("ChatMessage " + a + " " + b);
}
```

To call the method from any script, you need access to a **PhotonView** object. If your script derives from **PhotonMonoBehaviour**, it has a `photonView` field. Any regular MonoBehaviour or GameObject can use: `PhotonView.Get(this)` to get access to its **PhotonView** component and then call RPCs on it.

```
PhotonView photonView = PhotonView.Get(this);
photonView.RPC("ChatMessage", PhotonTargets.All, "jup", "and jup!");
```

So, instead of directly calling the target method, you call `RPC()` on a [PhotonView](#). Provide the name of the method to call, which players should call the method and then provide a list of parameters.

Careful: The parameters list used in `RPC()` has to match the number of expected parameters! If the receiving client can't find a matching method, it will log an error. There is one exception to this rule: The last parameter of a RPC method can be of type [PhotonMessageInfo](#), which will provide some context for each call.

```
[PunRPC]
void ChatMessage(string a, string b, PhotonMessageInfo info)
{
    Debug.Log(String.Format("Info: {0} {1} {2}", info.sender, info.photonView, info.timestamp));
}
```

Timing for RPCs and Loading Levels

RPCs are called on specific PhotonViews and always target the matching one on the remote client. If the remote client does not know the fitting [PhotonView](#), the RPC is lost.

A typical cause for lost RPCs is when clients load and set up levels. One client is faster or in the room for a longer time and sends important RPCs for objects that are not yet loaded on the other clients. The same happens when RPCs are buffered.

The solution is to pause the message queue, during scene loading. This code shows how you can do it:

```
private IEnumerator MoveToGameScene()
{
    // Temporary disable processing of further network messages
    PhotonNetwork.IsMessageQueueRunning = false;
    Application.LoadLevel(levelName);
}
```

Alternatively you can use [PhotonNetwork.LoadLevel](#). It temporarily disables the message queue as well.

Disabling the message queue will delay incoming and outgoing messages until the queue is unlocked. Obviously, it's very important to unlock the queue when you're ready to go on.

RPCs that belonged to the previously loaded scene but still arrived will now be discarded. But you should be able to define a break between both scenes by RPC.

Various topics

2.1.3 Instantiating Networked Objects

In about every game you need to instantiate one or more player objects for every player. There are various options to do so which are listed below.

[PhotonNetwork.Instantiate](#)

PUN can automatically take care of spawning an object by passing a starting position, rotation and a prefab name to the [PhotonNetwork.Instantiate](#) method. Requirement: The prefab should be available directly under a Resources/ folder so that the prefab can be loaded at run time. Watch out with webplayers: Everything in the resources folder will be streamed at the very first scene per default. Under the webplayer settings you can specify the first level that uses assets from the Resources folder by using the "First streamed level". If you set this to your first game scene, your preloader and mainmenu will not be slowed down if they don't use the Resources folder assets.

```
void SpawnMyPlayerEverywhere()
{
    PhotonNetwork.Instantiate("MyPrefabName", new Vector3(0,0,0), Quaternion.identity, 0);
    //The last argument is an optional group number, feel free to ignore it for now.
}
```

Gain more control: Manually instantiate

If don't want to rely on the Resources folders to instantiate objects over the network you'll have to manually instantiate objects as shown in the example at the end of this section.

The main reason for wanting to instantiate manually is gaining control over what is downloaded when for streaming webplayers. The details about streaming and the Resources folder in Unity can be found [here](#).

If you spawn manually, you will have to assign a PhotonViewID yourself, these viewID's are the key to routing network messages to the correct gameobject/scripts. The player who wants to own and spawn a new object should allocate a new viewID using [PhotonNetwork.AllocateViewID\(\)](#); This PhotonViewID should then be send to all other players using a [PhotonView](#) that has already been set up (for example an existing scene [PhotonView](#)). You will have to keep in mind that this RPC needs to be buffered so that any clients that connect later will also receive the spawn instructions. Then the RPC message that is used to spawn the object will need a reference to your desired prefab and instantiate this using Unity's `GameObject.Instantiate`. Finally you will need to set setup the PhotonViews attached to this prefab by assigning all PhotonViews a PhotonViewID.

```
void SpawnMyPlayerEverywhere()
{
    //Manually allocate PhotonViewID
    PhotonViewID id1 = PhotonNetwork.AllocateViewID();

    photonView.RPC("SpawnOnNetwork", PhotonTargets.AllBuffered, transform.position
    , transform.rotation, id1, PhotonNetwork.player);
}

public Transform playerPrefab; //set this in the inspector

[PunRPC]
void SpawnOnNetwork(Vector3 pos, Quaternion rot, PhotonViewID id1, PhotonPlayer np)
{
    Transform newPlayer = Instantiate(playerPrefab, pos, rot) as Transform;

    //Set the PhotonView
    PhotonView[] nViews = go.GetComponentsInChildren<PhotonView>();
    nViews[0].viewID = id1;
}
```

If you want to use asset bundles to load your network objects from, all you have to do is add your own assetbundle loading code and replace the "playerPrefab" from the example with the prefab from your asset bundle.

Offline mode

Offline mode is a feature to be able to re-use your multiplayer code in singleplayer game modes as well.

Mike Hergaarden: At M2H we had to rebuild our games several times as game portals usually require you to remove multiplayer functionality completely. Furthermore, being able to use the same code for single and multiplayer saves a lot of work on itself.

The most common features that you'll want to be able to use in singleplayer are sending RPCs and using [PhotonNetwork.Instantiate](#). The main goal of offline mode is to disable nullreferences and other errors when using [PhotonNetwork](#) functionality while not connected. You would still need to keep track of the fact that you're running a singleplayer game, to set up the game etc. However, while running the game, all code should be reusable.

You need to manually enable offline mode, as [PhotonNetwork](#) needs to be able to distinguish erroneous from intended behaviour. Enabling this feature is very easy:

```
PhotonNetwork.offlineMode = true;
```

You can now reuse certain multiplayer methods without generating any connections and errors. Furthermore there is no noticeable overhead. Below follows a list of [PhotonNetwork](#) functions and variables and their results during offline mode:

[PhotonNetwork.player](#) The player ID is always -1 [PhotonNetwork.playerName](#) Works as expected. [PhotonNetwork.playerList](#) Contains only the local player [PhotonNetwork.otherPlayers](#) Always empty [PhotonNetwork.time](#) returns Environment.TickCount or a more precise timer if enabled; [PhotonNetwork.isMasterClient](#) Always true

[PhotonNetwork.AllocateViewID\(\)](#) Works as expected. [PhotonNetwork.Instantiate](#) Works as expected [PhotonNetwork.Destroy](#) Works as expected. [PhotonNetwork.RemoveRPCs/RemoveRPCsInGroup/SetReceivingEnabled/SetSendingEnabled/SetLevelPrefix](#) While these make no sense in Singleplayer, they will not hurt either. [PhotonView.RPC](#) Works as expected.

Note that using other methods than the ones above can yield unexpected results and some will simply do nothing. E.g. [PhotonNetwork.room](#) will, obviously, return null. If you intend on starting a game in singleplayer, but move it to multiplayer at a later stage, you might want to consider hosting a 1 player game instead; this will preserve buffered RPCs and Instantiation calls, whereas offline mode Instantiations will not automatically carry over after Connecting.

Either set [PhotonNetwork.offlineMode](#) = false; or Simply call [Connect\(\)](#) to stop offline mode.

Limitations

Views and players

For performance reasons, the [PhotonNetwork](#) API supports up to 1000 PhotonViews per player and a maximum of 2,147,483 players (note that this is WAY higher than your hardware can support!). You can easily allow for more PhotonViews per player, at the cost of maximum players. This works as follows: PhotonViews send out a viewID for every network message. This viewID is an integer and it is composed of the player ID and the player's view ID. The maximum size of an int is 2,147,483,647, divided by our MAX_VIEW_IDS(1000) that allows for over 2 million players, each having 1000 view IDs. As you can see, you can easily increase the player count by reducing the MAX_VIEW_IDS. The other way around, you can give all players more VIEW_IDS at the cost of less maximum players. It is important to note that most games will never need more than a few view ID's per player (one or two for the character..and that's usually it). If you need much more then you might be doing something wrong! It is extremely inefficient to assign a [PhotonView](#) and ID for every bullet that your weapon fires, instead keep track of your fire bullets via the player or weapon's [PhotonView](#).

There is room for improving your bandwidth performance by reducing the int to a short (value range: 32,768 to 32,768). By setting MAX_VIEW_IDS to 32 you can then still support 1023 players Search for "//LIMITS NETWORK_VIEWS&PLAYERS" for all occurrences of the int viewID. Furthermore, currently the API is not using uint/ushort but only the positive range of the numbers. This is done for simplicity and the usage of viewIDs is not a crucial performance issue for most situations.

Groups and Scoping

The [PhotonNetwork](#) plugin does not support network groups fully. See above: "Using Groups in PUN".

Unity's "scope" feature is not implemented.

Feedback

We are interested in your feedback, as this solution is an ongoing project for us. Let us know if something was too hidden, missing or not working. To let us know, post in our Forum: forum.exitgames.com

F.A.Q.

Can I use multiple PhotonViews per GameObject? Why?

Yes this is perfectly fine. You will need multiple PhotonViews if you need to observe 2 or more targets; You can only observe one per [PhotonView](#). For your RPC's you'll only ever need one [PhotonView](#) and this can be the same [PhotonView](#) that is already observing something. RPC's never clash with an observed target.

Can I use UnityScript / Javascript?

To use PUN from UnityScript, move both folders "PhotonNetwork" and "UtilityScripts" to the Assets\ folder. Now PUN compiles before UnityScript and that makes it available from regular UnityScript code.

Chapter 3

Network Simulation GUI

Simple GUI element to control the built-in network condition simulation.

The Photon client library can simulate network conditions for lag (message delay) and loss, which can be a good tool for developer when testing with a local server or on near perfect network conditions.

To use it, add the component PhotonNetSimSettingsGui to an enabled GameObject in your scene. At runtime, the top left of the screen shows the current roundtrip time (RTT) and the controls for network simulation:

- RTT: The roundtrip time is the average of milliseconds until a message was acknowledged by the server. The variance value (behind the +/-) shows how stable the rtt is (a lower value being better).
- "Sim" toggle: Enables and disables the simulation. A sudden, big change of network conditions might result in disconnects.
- "Lag" slider: Adds a fixed delay to all outgoing and incoming messages. In milliseconds.
- "Jit" slider: Adds a random delay of "up to X milliseconds" per message.
- "Loss" slider: Drops the set percentage of messages. You can expect less than 2% drop in the internet today.

Chapter 4

Network Statistics GUI

The PhotonStatsGui is a simple GUI component to track and show network-metrics at runtime.

Usage

Just add the [PhotonStatsGui](#) component to any active GameObject in the hierarchy. A window appears (at runtime) and shows the message count.

A few toggles let you configure the window:

- buttons: Show buttons for "stats on", "reset stats" and "to log"
- traffic: Show lower level network traffic (bytes per direction)
- health: Show timing of sending, dispatches and their longest gaps

Message Statistics

The top most values showns are counter for "messages". Any operation, response and event are counted. Shown are the total count of outgoing, incoming and the sum of those messages as total and as average for the timespan that is tracked.

Traffic Statistics

These are the byte and packet counters. Anything that leaves or arrives via network is counted here. Even if there are few messages, they could be huge by accident and still cause less powerful clients to drop connection. You also see that there are packages sent when you don't send messages. They keeps the connection alive.

Health Statistics

The block beginning with "longest delta between" is about the performance of your client. We measure how much time passed between consecutive calls of send and dispatch. Usually they should be called ten times per second. If these values go beyond one second, you should check why Update() calls are delayed.

Button "Reset"

This resets the stats but keeps tracking them. This is useful to track message counts for different situations.

Button "To Log"

Pressing this simply logs the current stat values. This can be useful to have a overview how things evolved or just as reference.

Button "Stats On" (Enabling Traffic Stats)

The Photon library can track various network statistics but usually this feature is turned off. The PhotonStatsGui will enable the tracking and show those values.

The "stats on" toggle in the Gui controls if traffic stats are collected at all. The "Traffic Stats On" checkbox in the Inspector is the same value.

Chapter 5

Public API Module

The Public API module rounds up the most commonly used classes of PUN.

These classes are grouped into a "module" to make it easier to find the important stuff in PUN. Classes like [Photon↔Network](#) and [Photon.PunBehaviour](#) are good entry points to learn how to code with PUN.

Opposed to that, there are several classes that are for internal use by the PUN framework. Even some of the internally used classes are public. This is for ease of use and in parts a result of how Unity works.

[Open the Public API module](#)

Chapter 6

Module Documentation

6.1 Public API

Groups the most important classes that you need to understand early on.

Classes

- interface [IPunObservable](#)
Defines the `OnPhotonSerializeView` method to make it easy to implement correctly for observable scripts.
- interface [IPunCallbacks](#)
This interface is used as definition of all callback methods of PUN, except `OnPhotonSerializeView`. Preferably, implement them individually.
- class [Photon.PunBehaviour](#)
This class provides a `.photonView` and all callbacks/events that PUN can call. Override the events/methods you want to use.
- struct [PhotonMessageInfo](#)
Container class for info about a particular message, RPC or update.
- class [PhotonStream](#)
This container is used in `OnPhotonSerializeView()` to either provide incoming data of a [PhotonView](#) or for you to provide it.
- class [PhotonNetwork](#)
The main class to use the [PhotonNetwork](#) plugin. This class is static.
- class [PhotonPlayer](#)
Summarizes a "player" within a room, identified (in that room) by actorID.
- class [PhotonView](#)
PUN's `NetworkView` replacement class for networking. Use it like a `NetworkView`.
- class [Room](#)
This class resembles a room that PUN joins (or joined). The properties are settable as opposed to those of a [RoomInfo](#) and you can close or hide "your" room.
- class [RoomInfo](#)
A simplified room with just the info required to list and join, used for the room listing in the lobby. The properties are not settable (open, MaxPlayers, etc).

Enumerations

- enum [PhotonNetworkingMessage](#) {
[PhotonNetworkingMessage.OnConnectedToPhoton](#), [PhotonNetworkingMessage.OnLeftRoom](#), [PhotonNetworkingMessage.OnMasterClientSwitched](#), [PhotonNetworkingMessage.OnPhotonCreateRoomFailed](#),
[PhotonNetworkingMessage.OnPhotonJoinRoomFailed](#), [PhotonNetworkingMessage.OnCreatedRoom](#),

PhotonNetworkingMessage.OnJoinedLobby, PhotonNetworkingMessage.OnLeftLobby,
 PhotonNetworkingMessage.OnDisconnectedFromPhoton, PhotonNetworkingMessage.OnConnectionFail,
 PhotonNetworkingMessage.OnFailedToConnectToPhoton, PhotonNetworkingMessage.OnReceivedRoom↵
 ListUpdate,
 PhotonNetworkingMessage.OnJoinedRoom, PhotonNetworkingMessage.OnPhotonPlayerConnected,
 PhotonNetworkingMessage.OnPhotonPlayerDisconnected, PhotonNetworkingMessage.OnPhoton↵
 RandomJoinFailed,
 PhotonNetworkingMessage.OnConnectedToMaster, PhotonNetworkingMessage.OnPhotonSerializeView,
 PhotonNetworkingMessage.OnPhotonInstantiate, PhotonNetworkingMessage.OnPhotonMaxCcuReached,
 PhotonNetworkingMessage.OnPhotonCustomRoomPropertiesChanged, PhotonNetworkingMessage.On↵
 PhotonPlayerPropertiesChanged, PhotonNetworkingMessage.OnUpdatedFriendList, PhotonNetworking↵
 Message.OnCustomAuthenticationFailed,
 PhotonNetworkingMessage.OnCustomAuthenticationResponse, PhotonNetworkingMessage.OnWebRpc↵
 Response, PhotonNetworkingMessage.OnOwnershipRequest, PhotonNetworkingMessage.OnLobby↵
 StatisticsUpdate,
 PhotonNetworkingMessage.OnPhotonPlayerActivityChanged, PhotonNetworkingMessage.OnOwnership↵
 Transferred }

*This enum defines the set of MonoMessages [Photon](#) Unity Networking is using as callbacks. Implemented by Pun↵
 Behaviour.*

- enum [PhotonLogLevel](#) { [PhotonLogLevel.ErrorsOnly](#), [PhotonLogLevel.Informational](#), [PhotonLogLevel.Full](#) }

Used to define the level of logging output created by the PUN classes. Either log errors, info (some more) or full.

- enum [PhotonTargets](#) {
[PhotonTargets.All](#), [PhotonTargets.Others](#), [PhotonTargets.MasterClient](#), [PhotonTargets.AllBuffered](#),
[PhotonTargets.OthersBuffered](#), [PhotonTargets.AllViaServer](#), [PhotonTargets.AllBufferedViaServer](#) }

Enum of "target" options for RPCs. These define which remote clients get your RPC call.

- enum [ClientState](#) {
[ClientState.Uninitialized](#), [ClientState.PeerCreated](#), [ClientState.Queued](#), [ClientState.Authenticated](#),
[ClientState.JoinedLobby](#), [ClientState.DisconnectingFromMasterserver](#), [ClientState.ConnectingToGameserver](#),
[ClientState.ConnectedToGameserver](#),
[ClientState.Joining](#), [ClientState.Joined](#), [ClientState.Leaving](#), [ClientState.DisconnectingFromGameserver](#),
[ClientState.ConnectingToMasterserver](#), [ClientState.QueuedComingFromGameserver](#), [ClientState.↵
 Disconnecting](#), [ClientState.Disconnected](#),
[ClientState.ConnectedToMaster](#), [ClientState.ConnectingToNameServer](#), [ClientState.ConnectedToName↵
 Server](#), [ClientState.DisconnectingFromNameServer](#),
[ClientState.Authenticating](#) }

*Detailed connection / networking peer state. PUN implements a loadbalancing and authentication workflow "behind
 the scenes", so some states will automatically advance to some follow up state. Those states are commented with
 "(will-change)".*

- enum [DisconnectCause](#) {
[DisconnectCause.DisconnectByServerUserLimit](#) = [StatusCode.DisconnectByServerUserLimit](#), [Disconnect↵
 Cause.ExceptionOnConnect](#) = [StatusCode.ExceptionOnConnect](#), [DisconnectCause.DisconnectByServer↵
 Timeout](#) = [StatusCode.DisconnectByServer](#), [DisconnectCause.DisconnectByServerLogic](#) = [StatusCode.↵
 DisconnectByServerLogic](#),
[DisconnectCause.Exception](#) = [StatusCode.Exception](#), [DisconnectCause.InvalidAuthentication](#) = [Error↵
 Code.InvalidAuthentication](#), [DisconnectCause.MaxCcuReached](#) = [ErrorCode.MaxCcuReached](#), [Disconnect↵
 Cause.InvalidRegion](#) = [ErrorCode.InvalidRegion](#),
[DisconnectCause.SecurityExceptionOnConnect](#) = [StatusCode.SecurityExceptionOnConnect](#), [Disconnect↵
 Cause.DisconnectByClientTimeout](#) = [StatusCode.TimeoutDisconnect](#), [DisconnectCause.InternalReceive↵
 Exception](#) = [StatusCode.ExceptionOnReceive](#), [DisconnectCause.AuthenticationTicketExpired](#) = 32753 }

Summarizes the cause for a disconnect. Used in: [OnConnectionFail](#) and [OnFailedToConnectToPhoton](#).

Functions

- void [IPunObservable.OnPhotonSerializeView](#) ([PhotonStream](#) stream, [PhotonMessageInfo](#) info)

*Called by PUN several times per second, so that your script can write and read synchronization data for the [Photon↵
 View](#).*

6.1.1 Detailed Description

Groups the most important classes that you need to understand early on.

6.1.2 Enumeration Type Documentation

6.1.2.1 enum ClientState

Detailed connection / networking peer state. PUN implements a loadbalancing and authentication workflow "behind the scenes", so some states will automatically advance to some follow up state. Those states are commented with "(will-change)".

Enumerator

- Uninitialized** Not running. Only set before initialization and first use.
- PeerCreated** Created and available to connect.
- Queued** Not used at the moment.
- Authenticated** The application is authenticated. PUN usually joins the lobby now.(will-change) Unless AutoJoinLobby is false.
- JoinedLobby** Client is in the lobby of the Master Server and gets room listings.Use Join, Create or JoinRandom to get into a room to play.
- DisconnectingFromMasterserver** Disconnecting.(will-change)
- ConnectingToGameserver** Connecting to game server (to join/create a room and play).(will-change)
- ConnectedToGameserver** Similar to Connected state but on game server. Still in process to join/create room.(will-change)
- Joining** In process to join/create room (on game server).(will-change)
- Joined** Final state of a room join/create sequence. This client can now exchange events / call RPCs with other clients.
- Leaving** Leaving a room.(will-change)
- DisconnectingFromGameserver** Workflow is leaving the game server and will re-connect to the master server.(will-change)
- ConnectingToMasterserver** Workflow is connected to master server and will establish encryption and authenticate your app.(will-change)
- QueuedComingFromGameserver** Same Queued but coming from game server.(will-change)
- Disconnecting** PUN is disconnecting. This leads to Disconnected.(will-change)
- Disconnected** No connection is setup, ready to connect. Similar to PeerCreated.
- ConnectedToMaster** Final state for connecting to master without joining the lobby (AutoJoinLobby is false).
- ConnectingToNameServer** Client connects to the NameServer. This process includes low level connecting and setting up encryption. When done, state becomes ConnectedToNameServer.
- ConnectedToNameServer** Client is connected to the NameServer and established encryption already. You should call OpGetRegions or ConnectToRegionMaster.
- DisconnectingFromNameServer** When disconnecting from a Photon NameServer.(will-change)
- Authenticating** When connecting to a Photon Server, this state is intermediate before you can call any operations.(will-change)

6.1.2.2 enum DisconnectCause

Summarizes the cause for a disconnect. Used in: OnConnectionFail and OnFailedToConnectToPhoton.

Extracted from the status codes from ExitGames.Client.Photon.StatusCode.

See also

[PhotonNetworkingMessage](#)

Enumerator

DisconnectByServerUserLimit Server actively disconnected this client. Possible cause: The server's user limit was hit and client was forced to disconnect (on connect).

ExceptionOnConnect Connection could not be established. Possible cause: Local server not running.

DisconnectByServerTimeout Timeout disconnect by server (which decided an ACK was missing for too long).

DisconnectByServerLogic Server actively disconnected this client. Possible cause: Server's send buffer full (too much data for client).

Exception Some exception caused the connection to close.

InvalidAuthentication (32767) The [Photon](#) Cloud rejected the sent Appld. Check your Dashboard and make sure the Appld you use is complete and correct.

MaxCcuReached (32757) Authorization on the [Photon](#) Cloud failed because the concurrent users (CCU) limit of the app's subscription is reached.

InvalidRegion (32756) Authorization on the [Photon](#) Cloud failed because the app's subscription does not allow to use a particular region's server.

SecurityExceptionOnConnect The security settings for client or server don't allow a connection (see remarks). A common cause for this is that browser clients read a "crossdomain" file from the server. If that file is unavailable or not configured to let the client connect, this exception is thrown. [Photon](#) usually provides this crossdomain file for Unity. If it fails, read: <http://doc.exitgames.com/photon-server/PolicyApp>

DisconnectByClientTimeout Timeout disconnect by client (which decided an ACK was missing for too long).

InternalReceiveException Exception in the receive-loop. Possible cause: Socket failure.

AuthenticationTicketExpired (32753) The Authentication ticket expired. Handle this by connecting again (which includes an authenticate to get a fresh ticket).

6.1.2.3 enum PhotonLogLevel

Used to define the level of logging output created by the PUN classes. Either log errors, info (some more) or full.

Enumerator

ErrorsOnly Show only errors. Minimal output. Note: Some might be "runtime errors" which you have to expect.

Informational Logs some of the workflow, calls and results.

Full Every available log call gets into the console/log. Only use for debugging.

6.1.2.4 enum PhotonNetworkingMessage

This enum defines the set of MonoMessages [Photon](#) Unity Networking is using as callbacks. Implemented by PunBehaviour.

Much like "Update()" in Unity, PUN will call methods in specific situations. Often, these methods are triggered when network operations complete (example: when joining a room).

All those methods are defined and described in this enum and implemented by PunBehaviour (which makes it easy to implement them as override).

Each entry is the name of such a method and the description tells you when it gets used by PUN.

Make sure to read the remarks per entry as some methods have optional parameters.

Enumerator

OnConnectedToPhoton Called when the initial connection got established but before you can use the server. [OnJoinedLobby\(\)](#) or [OnConnectedToMaster\(\)](#) are called when PUN is ready. This callback is only useful to detect if the server can be reached at all (technically). Most often, it's enough to implement [OnFailedToConnectToPhoton\(\)](#) and [OnDisconnectedFromPhoton\(\)](#).

[OnJoinedLobby\(\)](#) or [OnConnectedToMaster\(\)](#) are called when PUN is ready.

When this is called, the low level connection is established and PUN will send your AppId, the user, etc in the background. This is not called for transitions from the masterserver to game servers.

Example: void [OnConnectedToPhoton\(\)](#) { ... }

OnLeftRoom Called when the local user/client left a room. When leaving a room, PUN brings you back to the Master Server. Before you can use lobbies and join or create rooms, [OnJoinedLobby\(\)](#) or [OnConnectedToMaster\(\)](#) will get called again.

Example: void [OnLeftRoom\(\)](#) { ... }

OnMasterClientSwitched Called after switching to a new MasterClient when the current one leaves. This is not called when this client enters a room. The former MasterClient is still in the player list when this method get called.

Example: void OnMasterClientSwitched(PhotonPlayer newMasterClient) { ... }

OnPhotonCreateRoomFailed Called when a [CreateRoom\(\)](#) call failed. Optional parameters provide [Error↵Code](#) and message. Most likely because the room name is already in use (some other client was faster than you). PUN logs some info if the [PhotonNetwork.logLevel](#) is \geq [PhotonLogLevel.Informational](#).

Example: void [OnPhotonCreateRoomFailed\(\)](#) { ... }

Example: void OnPhotonCreateRoomFailed(object[] codeAndMsg) { // codeAndMsg[0] is short [Error↵Code](#). codeAndMsg[1] is string debug msg. }

OnPhotonJoinRoomFailed Called when a [JoinRoom\(\)](#) call failed. Optional parameters provide [ErrorCode](#) and message. Most likely error is that the room does not exist or the room is full (some other client was faster than you). PUN logs some info if the [PhotonNetwork.logLevel](#) is \geq [PhotonLogLevel.Informational](#).

Example: void [OnPhotonJoinRoomFailed\(\)](#) { ... }

Example: void OnPhotonJoinRoomFailed(object[] codeAndMsg) { // codeAndMsg[0] is short [ErrorCode](#). codeAndMsg[1] is string debug msg. }

OnCreatedRoom Called when this client created a room and entered it. [OnJoinedRoom\(\)](#) will be called as well. This callback is only called on the client which created a room (see [PhotonNetwork.CreateRoom\(\)](#)).

As any client might close (or drop connection) anytime, there is a chance that the creator of a room does not execute OnCreatedRoom.

If you need specific room properties or a "start signal", it is safer to implement [OnMasterClientSwitched\(\)](#) and to make the new MasterClient check the room's state.

Example: void [OnCreatedRoom\(\)](#) { ... }

OnJoinedLobby Called on entering a lobby on the Master Server. The actual room-list updates will call [OnReceivedRoomListUpdate\(\)](#). Note: When [PhotonNetwork.autoJoinLobby](#) is false, [OnConnectedTo↵Master\(\)](#) will be called and the room list won't become available.

While in the lobby, the roomlist is automatically updated in fixed intervals (which you can't modify). The room list gets available when [OnReceivedRoomListUpdate\(\)](#) gets called after [OnJoinedLobby\(\)](#).

Example: void [OnJoinedLobby\(\)](#) { ... }

OnLeftLobby Called after leaving a lobby. When you leave a lobby, [CreateRoom](#) and [JoinRandomRoom](#) automatically refer to the default lobby.

Example: void [OnLeftLobby\(\)](#) { ... }

OnDisconnectedFromPhoton Called after disconnecting from the [Photon](#) server. In some cases, other callbacks are called before OnDisconnectedFromPhoton is called. Examples: [OnConnectionFail\(\)](#) and [On↵FailedToConnectToPhoton\(\)](#).

Example: void [OnDisconnectedFromPhoton\(\)](#) { ... }

OnConnectionFail Called when something causes the connection to fail (after it was established), followed by a call to [OnDisconnectedFromPhoton\(\)](#). If the server could not be reached in the first place, [OnFailed↵ToConnectToPhoton](#) is called instead. The reason for the error is provided as [StatusCode](#).

Example: void OnConnectionFail(DisconnectCause cause) { ... }

OnFailedToConnectToPhoton Called if a connect call to the [Photon](#) server failed before the connection was established, followed by a call to [OnDisconnectedFromPhoton\(\)](#). [OnConnectionFail](#) only gets called when a connection to a [Photon](#) server was established in the first place.

Example: `void OnFailedToConnectToPhoton(DisconnectCause cause) { ... }`

OnReceivedRoomListUpdate Called for any update of the room-listing while in a lobby ([PhotonNetwork.JoinLobby\(\)](#) on the Master Server. PUN provides the list of rooms by [PhotonNetwork.GetRoomList\(\)](#). Each item is a [RoomInfo](#) which might include custom properties (provided you defined those as lobby-listed when creating a room).

Not all types of lobbies provide a listing of rooms to the client. Some are silent and specialized for server-side matchmaking.

Example: `void OnReceivedRoomListUpdate() { ... }`

OnJoinedRoom Called when entering a room (by creating or joining it). Called on all clients (including the Master Client). This method is commonly used to instantiate player characters. If a match has to be started "actively", you can instead call an [PunRPC](#) triggered by a user's button-press or a timer.

When this is called, you can usually already access the existing players in the room via [PhotonNetwork.CurrentRoom.playerList](#). Also, all custom properties should be already available as [Room.customProperties](#). Check [Room.playerCount](#) to find out if enough players are in the room to start playing.

Example: `void OnJoinedRoom() { ... }`

OnPhotonPlayerConnected Called when a remote player entered the room. This [PhotonPlayer](#) is already added to the playerlist at this time. If your game starts with a certain number of players, this callback can be useful to check the [Room.playerCount](#) and find out if you can start.

Example: `void OnPhotonPlayerConnected(PhotonPlayer newPlayer) { ... }`

OnPhotonPlayerDisconnected Called when a remote player left the room. This [PhotonPlayer](#) is already removed from the playerlist at this time. When your client calls [PhotonNetwork.leaveRoom](#), PUN will call this method on the remaining clients. When a remote client drops connection or gets closed, this callback gets executed. after a timeout of several seconds.

Example: `void OnPhotonPlayerDisconnected(PhotonPlayer otherPlayer) { ... }`

OnPhotonRandomJoinFailed Called after a [JoinRandom\(\)](#) call failed. Optional parameters provide [Error.Code](#) and message. Most likely all rooms are full or no rooms are available. When using multiple lobbies (via [JoinLobby](#) or [TypedLobby](#)), another lobby might have more/fitting rooms. PUN logs some info if the [PhotonNetwork.logLevel](#) is \geq [PhotonLogLevel.Informational](#).

Example: `void OnPhotonRandomJoinFailed() { ... }`

Example: `void OnPhotonRandomJoinFailed(object[] codeAndMsg) { // codeAndMsg[0] is short Error.Code. codeAndMsg[1] is string debug msg. }`

OnConnectedToMaster Called after the connection to the master is established and authenticated but only when [PhotonNetwork.autoJoinLobby](#) is false. If you set [PhotonNetwork.autoJoinLobby](#) to true, [OnJoinedLobby\(\)](#) will be called instead of this.

You can join rooms and create them even without being in a lobby. The default lobby is used in that case. The list of available rooms won't become available unless you join a lobby via [PhotonNetwork.joinLobby](#).

Example: `void OnConnectedToMaster() { ... }`

OnPhotonSerializeView Implement to customize the data a [PhotonView](#) regularly synchronizes. Called every 'network-update' when observed by [PhotonView](#). This method will be called in scripts that are assigned as Observed component of a [PhotonView](#). [PhotonNetwork.sendRateOnSerialize](#) affects how often this method is called. [PhotonNetwork.sendRate](#) affects how often packages are sent by this client.

Implementing this method, you can customize which data a [PhotonView](#) regularly synchronizes. Your code defines what is being sent (content) and how your data is used by receiving clients.

Unlike other callbacks, *OnPhotonSerializeView only gets called when it is assigned to a [PhotonView](#) as [PhotonView.observed](#) script.*

To make use of this method, the [PhotonStream](#) is essential. It will be in "writing" mode" on the client that controls a [PhotonView](#) ([PhotonStream.isWriting](#) == true) and in "reading mode" on the remote clients that just receive that the controlling client sends.

If you skip writing any value into the stream, PUN will skip the update. Used carefully, this can conserve bandwidth and messages (which have a limit per room/second).

Note that `OnPhotonSerializeView` is not called on remote clients when the sender does not send any update. This can't be used as "x-times per second Update()".

Example: `void OnPhotonSerializeView(PhotonStream stream, PhotonMessageInfo info) { ... }`

OnPhotonInstantiate Called on all scripts on a `GameObject` (and children) that have been Instantiated using [PhotonNetwork.Instantiate](#). [PhotonMessageInfo](#) parameter provides info about who created the object and when (based off `PhotonNetworking.time`).

Example: `void OnPhotonInstantiate(PhotonMessageInfo info) { ... }`

OnPhotonMaxCccuReached Because the concurrent user limit was (temporarily) reached, this client is rejected by the server and disconnecting. When this happens, the user might try again later. You can't create or join rooms in `OnPhotonMaxCcuReached()`, cause the client will be disconnecting. You can raise the CCU limits with a new license (when you host yourself) or extended subscription (when using the [Photon Cloud](#)). The [Photon Cloud](#) will mail you when the CCU limit was reached. This is also visible in the Dashboard (webpage).

Example: `void OnPhotonMaxCccuReached() { ... }`

OnPhotonCustomRoomPropertiesChanged Called when a room's custom properties changed. The `propertiesThatChanged` contains all that was set via [Room.SetCustomProperties](#). Since v1.25 this method has one parameter: `Hashtable propertiesThatChanged`. Changing properties must be done by [Room.SetCustomProperties](#), which causes this callback locally, too.

Example: `void OnPhotonCustomRoomPropertiesChanged(Hashtable propertiesThatChanged) { ... }`

OnPhotonPlayerPropertiesChanged Called when custom player-properties are changed. Player and the changed properties are passed as `object[]`. Since v1.25 this method has one parameter: `object[] playerAndUpdatedProps`, which contains two entries.
[0] is the affected [PhotonPlayer](#).
[1] is the `Hashtable` of properties that changed.

We are using a `object[]` due to limitations of Unity's `GameObject.SendMessage` (which has only one optional parameter).

Changing properties must be done by [PhotonPlayer.SetCustomProperties](#), which causes this callback locally, too.

Example:

```
void OnPhotonPlayerPropertiesChanged(object[] playerAndUpdatedProps) {
    PhotonPlayer player = playerAndUpdatedProps[0] as PhotonPlayer;
    Hashtable props = playerAndUpdatedProps[1] as Hashtable;
    //...
}
```

OnUpdatedFriendList Called when the server sent the response to a `FindFriends` request and updated [PhotonNetwork.Friends](#). The friends list is available as [PhotonNetwork.Friends](#), listing name, online state and the room a user is in (if any).

Example: `void OnUpdatedFriendList() { ... }`

OnCustomAuthenticationFailed Called when the custom authentication failed. Followed by `disconnect!` Custom Authentication can fail due to user-input, bad tokens/secrets. If authentication is successful, this method is not called. Implement [OnJoinedLobby\(\)](#) or [OnConnectedToMaster\(\)](#) (as usual).

During development of a game, it might also fail due to wrong configuration on the server side. In those cases, logging the `debugMessage` is very important.

Unless you setup a custom authentication service for your app (in the [Dashboard](#)), this won't be called!

Example: `void OnCustomAuthenticationFailed(string debugMessage) { ... }`

OnCustomAuthenticationResponse Called when your Custom Authentication service responds with additional data. Custom Authentication services can include some custom data in their response. When present, that data is made available in this callback as `Dictionary`. While the keys of your data have to be strings, the values can be either string or a number (in `Json`). You need to make extra sure, that the value type is the one you expect. Numbers become (currently) `int64`.

Example: `void OnCustomAuthenticationResponse(Dictionary<string, object> data) { ... }`

<https://doc.photonengine.com/en/realtime/current/reference/custom-authentication>

OnWebRpcResponse Called by PUN when the response to a WebRPC is available. See PhotonNetwork.↔ WebRPC. Important: The response.ReturnCode is 0 if Photon was able to reach your web-service. The content of the response is what your web-service sent. You can create a WebResponse instance from it. Example: `WebRpcResponse webResponse = new WebRpcResponse(operationResponse);`

Please note: Class OperationResponse is in a namespace which needs to be "used": using `ExitGames.↔ Client.Photon;` // includes OperationResponse (and other classes)

The OperationResponse.ReturnCode by Photon is: 0 for "OK" -3 for "Web-Service not configured" (see Dashboard / WebHooks) -5 for "Web-Service does now have RPC path/name" (at least for Azure)

Example: `void OnWebRpcResponse(OperationResponse response) { ... }`

OnOwnershipRequest Called when another player requests ownership of a PhotonView from you (the current owner). The parameter viewAndPlayer contains:

`PhotonView view = viewAndPlayer[0] as PhotonView;`

`PhotonPlayer requestingPlayer = viewAndPlayer[1] as PhotonPlayer;`

`void OnOwnershipRequest(object[] viewAndPlayer) {} //`

OnLobbyStatisticsUpdate Called when the Master Server sent an update for the Lobby Statistics, updating PhotonNetwork.LobbyStatistics. This callback has two preconditions: EnableLobbyStatistics must be set to true, before this client connects. And the client has to be connected to the Master Server, which is providing the info about lobbies.

OnPhotonPlayerActivityChanged Called when a remote Photon Player activity changed. This will be called ONLY if PlayerTtl is greater than 0. Use `PhotonPlayer.IsInactive` to check the current activity state

Example: `void OnPhotonPlayerActivityChanged(PhotonPlayer otherPlayer) {...}`

This callback has precondition: PlayerTtl must be greater than 0

OnOwnershipTransferred Called when a PhotonView Owner is transferred to a Player. The parameter view↔ AndPlayers contains:

`PhotonView view = viewAndPlayers[0] as PhotonView;`

`PhotonPlayer newOwner = viewAndPlayers[1] as PhotonPlayer;`

`PhotonPlayer oldOwner = viewAndPlayers[2] as PhotonPlayer;`

`void OnOwnershipTransferred(object[] viewAndPlayers) {} //`

6.1.2.5 enum PhotonTargets

Enum of "target" options for RPCs. These define which remote clients get your RPC call.

Enumerator

All Sends the RPC to everyone else and executes it immediately on this client. Player who join later will not execute this RPC.

Others Sends the RPC to everyone else. This client does not execute the RPC. Player who join later will not execute this RPC.

MasterClient Sends the RPC to MasterClient only. Careful: The MasterClient might disconnect before it executes the RPC and that might cause dropped RPCs.

AllBuffered Sends the RPC to everyone else and executes it immediately on this client. New players get the RPC when they join as it's buffered (until this client leaves).

OthersBuffered Sends the RPC to everyone. This client does not execute the RPC. New players get the RPC when they join as it's buffered (until this client leaves).

AllViaServer Sends the RPC to everyone (including this client) through the server. This client executes the RPC like any other when it received it from the server. Benefit: The server's order of sending the RPCs is the same on all clients.

AllBufferedViaServer Sends the RPC to everyone (including this client) through the server and buffers it for players joining later. This client executes the RPC like any other when it received it from the server. Benefit: The server's order of sending the RPCs is the same on all clients.

6.1.3 Function Documentation

6.1.3.1 void IPunObservable.OnPhotonSerializeView (PhotonStream stream, PhotonMessageInfo info)

Called by PUN several times per second, so that your script can write and read synchronization data for the [PhotonView](#).

This method will be called in scripts that are assigned as Observed component of a [PhotonView](#).

[PhotonNetwork.sendRateOnSerialize](#) affects how often this method is called.

[PhotonNetwork.sendRate](#) affects how often packages are sent by this client.

Implementing this method, you can customize which data a [PhotonView](#) regularly synchronizes. Your code defines what is being sent (content) and how your data is used by receiving clients.

Unlike other callbacks, *OnPhotonSerializeView only gets called when it is assigned to a [PhotonView](#) as PhotonView.observed script.*

To make use of this method, the [PhotonStream](#) is essential. It will be in "writing" mode" on the client that controls a PhotonView (PhotonStream.isWriting == true) and in "reading mode" on the remote clients that just receive that the controlling client sends.

If you skip writing any value into the stream, PUN will skip the update. Used carefully, this can conserve bandwidth and messages (which have a limit per room/second).

Note that OnPhotonSerializeView is not called on remote clients when the sender does not send any update. This can't be used as "x-times per second Update()".

Implemented in [PhotonAnimatorView](#), [PhotonTransformView](#), [PhotonRigidbody2DView](#), and [PhotonRigidbodyView](#).

6.2 Optional Gui Elements

Useful GUI elements for PUN.

Classes

- class [PhotonLagSimulationGui](#)

This MonoBehaviour is a basic GUI for the [Photon](#) client's network-simulation feature. It can modify lag (fixed delay), jitter (random lag) and packet loss.

- class [PhotonStatsGui](#)

Basic GUI to show traffic and health statistics of the connection to [Photon](#), toggled by shift+tab.

6.2.1 Detailed Description

Useful GUI elements for PUN.

Chapter 7

Namespace Documentation

7.1 Package ExitGames

Namespaces

- package [Client](#)

7.2 Package ExitGames.Client

Namespaces

- package [GUI](#)
- package [Photon](#)

7.3 Package ExitGames.Client.GUI

Classes

- class [GizmoTypeDrawer](#)

Enumerations

- enum [GizmoType](#) { [GizmoType.WireSphere](#), [GizmoType.Sphere](#), [GizmoType.WireCube](#), [GizmoType.Cube](#) }

7.3.1 Enumeration Type Documentation

7.3.1.1 enum ExitGames.Client.GUI.GizmoType

Enumerator

WireSphere

Sphere

WireCube

Cube

7.4 Package ExitGames.Client.Photon

Namespaces

- package [Chat](#)

7.5 Package ExitGames.Client.Photon.Chat

Classes

- class [AuthenticationValues](#)
Container for user authentication in [Photon](#). Set AuthValues before you connect - all else is handled.
- class [ChatChannel](#)
A channel of communication in [Photon Chat](#), updated by [ChatClient](#) and provided as READ ONLY.
- class [ChatClient](#)
Central class of the [Photon Chat](#) API to connect, handle channels and messages.
- class [ChatEventCode](#)
Wraps up internally used constants in [Photon Chat](#) events. You don't have to use them directly usually.
- class [ChatOperationCode](#)
Wraps up codes for operations used internally in [Photon Chat](#). You don't have to use them directly usually.
- class [ChatParameterCode](#)
Wraps up codes for parameters (in operations and events) used internally in [Photon Chat](#). You don't have to use them directly usually.
- class [ChatPeer](#)
Provides basic operations of the [Photon Chat](#) server. This internal class is used by public [ChatClient](#).
- class [ChatUserStatus](#)
Contains commonly used status values for SetOnlineStatus. You can define your own.
- class [ErrorCode](#)
[ErrorCode](#) defines the default codes associated with [Photon](#) client/server communication.
- interface [IChatClientListener](#)
Callback interface for [Chat](#) client side. Contains callback methods to notify your app about updates. Must be provided to new [ChatClient](#) in constructor
- class [ParameterCode](#)

Enumerations

- enum [ChatDisconnectCause](#) {
[ChatDisconnectCause.None](#), [ChatDisconnectCause.DisconnectByServerUserLimit](#), [ChatDisconnectCause.ExceptionOnConnect](#), [ChatDisconnectCause.DisconnectByServer](#),
[ChatDisconnectCause.TimeoutDisconnect](#), [ChatDisconnectCause.Exception](#), [ChatDisconnectCause.InvalidAuthentication](#), [ChatDisconnectCause.MaxCcuReached](#),
[ChatDisconnectCause.InvalidRegion](#), [ChatDisconnectCause.OperationNotAllowedInCurrentState](#), [ChatDisconnectCause.CustomAuthenticationFailed](#) }
Enumeration of causes for Disconnects (used in LoadBalancingClient.DisconnectedCause).
- enum [CustomAuthenticationType](#) : byte {
[CustomAuthenticationType.Custom](#) = 0, [CustomAuthenticationType.Steam](#) = 1, [CustomAuthenticationType.Facebook](#) = 2, [CustomAuthenticationType.Oculus](#) = 3,
[CustomAuthenticationType.PlayStation](#) = 4, [CustomAuthenticationType.Xbox](#) = 5, [CustomAuthenticationType.None](#) = byte.MaxValue }
Options for optional "Custom Authentication" services used with [Photon](#). Used by OpAuthenticate after connecting to [Photon](#).

- enum ChatState {
 ChatState.Uninitialized, ChatState.ConnectingToNameServer, ChatState.ConnectedToNameServer, ChatState.Authenticating,
 ChatState.Authenticated, ChatState.DisconnectingFromNameServer, ChatState.ConnectingToFrontEnd,
 ChatState.ConnectedToFrontEnd,
 ChatState.DisconnectingFromFrontEnd, ChatState.QueuedComingFromFrontEnd, ChatState.Disconnecting,
 ChatState.Disconnected }

Possible states for a LoadBalancingClient.

7.5.1 Enumeration Type Documentation

7.5.1.1 enum ExitGames.Client.Photon.Chat.ChatDisconnectCause

Enumeration of causes for Disconnects (used in LoadBalancingClient.DisconnectedCause).

Read the individual descriptions to find out what to do about this type of disconnect.

Enumerator

None No error was tracked.

DisconnectByServerUserLimit OnStatusChanged: The CCUs count of your Photon Server License is exhausted (temporarily).

ExceptionOnConnect OnStatusChanged: The server is not available or the address is wrong. Make sure the port is provided and the server is up.

DisconnectByServer OnStatusChanged: The server disconnected this client. Most likely the server's send buffer is full (receiving too much from other clients).

TimeoutDisconnect OnStatusChanged: This client detected that the server's responses are not received in due time. Maybe you send / receive too much?

Exception OnStatusChanged: Some internal exception caused the socket code to fail. Contact Exit Games.

InvalidAuthentication OnOperationResponse: Authenticate in the Photon Cloud with invalid AppId. Update your subscription or contact Exit Games.

MaxCcuReached OnOperationResponse: Authenticate (temporarily) failed when using a Photon Cloud subscription without CCU Burst. Update your subscription.

InvalidRegion OnOperationResponse: Authenticate when the app's Photon Cloud subscription is locked to some (other) region(s). Update your subscription or master server address.

OperationNotAllowedInCurrentState OnOperationResponse: Operation that's (currently) not available for this client (not authorized usually). Only tracked for op Authenticate.

CustomAuthenticationFailed OnOperationResponse: Authenticate in the Photon Cloud with invalid client values or custom authentication setup in Cloud Dashboard.

7.5.1.2 enum ExitGames.Client.Photon.Chat.ChatState

Possible states for a LoadBalancingClient.

Enumerator

Uninitialized Peer is created but not used yet.

ConnectingToNameServer Connecting to master (includes connect, authenticate and joining the lobby)

ConnectedToNameServer Connected to master server.

Authenticating Usually when Authenticated, the client will join a game or the lobby (if AutoJoinLobby is true).

Authenticated Usually when Authenticated, the client will join a game or the lobby (if AutoJoinLobby is true).

DisconnectingFromNameServer Transition from master to game server.

ConnectingToFrontEnd Transition to gameserver (client will authenticate and join/create game).

ConnectedToFrontEnd Connected to gameserver (going to auth and join game).

DisconnectingFromFrontEnd Transition from gameserver to master (after leaving a room/game).

QueuedComingFromFrontEnd Currently not used.

Disconnecting The client disconnects (from any server).

Disconnected The client is no longer connected (to any server). Connect to master to go on.

7.5.1.3 enum ExitGames.Client.Photon.Chat.CustomAuthenticationType : byte

Options for optional "Custom Authentication" services used with [Photon](#). Used by OpAuthenticate after connecting to [Photon](#).

Enumerator

Custom Use a custom authentication service. Currently the only implemented option.

Steam Authenticates users by their Steam Account. Set auth values accordingly!

Facebook Authenticates users by their Facebook Account. Set auth values accordingly!

Oculus Authenticates users by their Oculus Account and token.

PlayStation Authenticates users by their PSN Account and token.

Xbox Authenticates users by their Xbox Account and XSTS token.

None Disables custom authentication. Same as not providing any [AuthenticationValues](#) for connect (more precisely for: OpAuthenticate).

7.6 Package Photon

Classes

- class [MonoBehaviour](#)

This class adds the property photonView, while logging a warning when your game still uses the networkView.

- class [PunBehaviour](#)

This class provides a .photonView and all callbacks/events that PUN can call. Override the events/methods you want to use.

Typedefs

- using [Hashtable](#) = ExitGames.Client.Photon.Hashtable

7.6.1 Typedef Documentation

7.6.1.1 using Photon.Hashtable = typedef ExitGames.Client.Photon.Hashtable

7.7 Package UnityEngine

Namespaces

- package [SceneManagement](#)

7.8 Package UnityEngine.SceneManagement

Classes

- class [SceneManager](#)

Minimal implementation of the [SceneManager](#) for older Unity, up to v5.2.

Chapter 8

Class Documentation

8.1 ActorProperties Class Reference

Class for constants. These (byte) values define "well known" properties for an Actor / Player.

Public Attributes

- const byte [PlayerName](#) = 255
(255) Name of a player/actor.
- const byte [IsInactive](#) = 254
(254) Tells you if the player is currently in this game (getting events live).
- const byte [UserId](#) = 253
(253) UserId of the player. Sent when room gets created with [RoomOptions.PublishUserId](#) = true.

8.1.1 Detailed Description

Class for constants. These (byte) values define "well known" properties for an Actor / Player.

Pun uses these constants internally. "Custom properties" have to use a string-type as key. They can be assigned at will.

8.1.2 Member Data Documentation

8.1.2.1 const byte ActorProperties.IsInactive = 254

(254) Tells you if the player is currently in this game (getting events live).

A server-set value for async games, where players can leave the game and return later.

8.1.2.2 const byte ActorProperties.PlayerName = 255

(255) Name of a player/actor.

8.1.2.3 const byte ActorProperties.UserId = 253

(253) UserId of the player. Sent when room gets created with [RoomOptions.PublishUserId](#) = true.

8.2 ExitGames.Client.Photon.Chat.AuthenticationValues Class Reference

Container for user authentication in [Photon](#). Set AuthValues before you connect - all else is handled.

Public Member Functions

- [AuthenticationValues](#) ()
Creates empty auth values without any info.
- [AuthenticationValues](#) (string userId)
Creates minimal info about the user. If this is authenticated or not, depends on the set AuthType.
- virtual void [SetAuthPostData](#) (string stringData)
Sets the data to be passed-on to the auth service via POST.
- virtual void [SetAuthPostData](#) (byte[] byteData)
Sets the data to be passed-on to the auth service via POST.
- virtual void [AddAuthParameter](#) (string key, string value)
Adds a key-value pair to the get-parameters used for Custom Auth.
- override string [ToString](#) ()

Properties

- [CustomAuthenticationType AuthType](#) [get, set]
The type of custom authentication provider that should be used. Currently only "Custom" or "None" (turns this off).
- string [AuthGetParameters](#) [get, set]
This string must contain any (http get) parameters expected by the used authentication service. By default, username and token.
- object [AuthPostData](#) [get, set]
Data to be passed-on to the auth service via POST. Default: null (not sent). Either string or byte[] (see setters).
- string [Token](#) [get, set]
After initial authentication, [Photon](#) provides a token for this client / user, which is subsequently used as (cached) validation.
- string [UserId](#) [get, set]
The UserId should be a unique identifier per user. This is for finding friends, etc..

8.2.1 Detailed Description

Container for user authentication in [Photon](#). Set AuthValues before you connect - all else is handled.

On [Photon](#), user authentication is optional but can be useful in many cases. If you want to FindFriends, a unique ID per user is very practical.

There are basically three options for user authentication: None at all, the client sets some UserId or you can use some account web-service to authenticate a user (and set the UserId server-side).

Custom Authentication lets you verify end-users by some kind of login or token. It sends those values to [Photon](#) which will verify them before granting access or disconnecting the client.

The [Photon](#) Cloud Dashboard will let you enable this feature and set important server values for it. <https://www.photonengine.com/dashboard>

8.2.2 Constructor & Destructor Documentation

8.2.2.1 ExitGames.Client.Photon.Chat.AuthenticationValues.AuthenticationValues ()

Creates empty auth values without any info.

8.2.2.2 ExitGames.Client.Photon.Chat.AuthenticationValues.AuthenticationValues (string *userId*)

Creates minimal info about the user. If this is authenticated or not, depends on the set AuthType.

Parameters

<i>userId</i>	Some UserId to set in Photon .
---------------	--

8.2.3 Member Function Documentation

8.2.3.1 `virtual void ExitGames.Client.Photon.Chat.AuthenticationValues.AddAuthParameter (string key, string value)` [virtual]

Adds a key-value pair to the get-parameters used for Custom Auth.

This method does uri-encoding for you.

Parameters

<i>key</i>	Key for the value to set.
<i>value</i>	Some value relevant for Custom Authentication.

8.2.3.2 `virtual void ExitGames.Client.Photon.Chat.AuthenticationValues.SetAuthPostData (string stringData)` [virtual]

Sets the data to be passed-on to the auth service via POST.

Parameters

<i>stringData</i>	String data to be used in the body of the POST request. Null or empty string will set Auth↵PostData to null.
-------------------	--

8.2.3.3 `virtual void ExitGames.Client.Photon.Chat.AuthenticationValues.SetAuthPostData (byte[] byteData)` [virtual]

Sets the data to be passed-on to the auth service via POST.

Parameters

<i>byteData</i>	Binary token / auth-data to pass on.
-----------------	--------------------------------------

8.2.3.4 `override string ExitGames.Client.Photon.Chat.AuthenticationValues.ToString ()`

8.2.4 Property Documentation

8.2.4.1 `string ExitGames.Client.Photon.Chat.AuthenticationValues.AuthGetParameters` [get], [set]

This string must contain any (http get) parameters expected by the used authentication service. By default, user-name and token.

Standard http get parameters are used here and passed on to the service that's defined in the server ([Photon](#) Cloud Dashboard).

8.2.4.2 `object ExitGames.Client.Photon.Chat.AuthenticationValues.AuthPostData` [get], [set]

Data to be passed-on to the auth service via POST. Default: null (not sent). Either string or byte[] (see setters).

8.2.4.3 `CustomAuthenticationType ExitGames.Client.Photon.Chat.AuthenticationValues.AuthType` [get], [set]

The type of custom authentication provider that should be used. Currently only "Custom" or "None" (turns this off).

8.2.4.4 string `ExitGames.Client.Photon.Chat.AuthenticationValues.Token` [get], [set]

After initial authentication, [Photon](#) provides a token for this client / user, which is subsequently used as (cached) validation.

8.2.4.5 string `ExitGames.Client.Photon.Chat.AuthenticationValues.UserId` [get], [set]

The `UserId` should be a unique identifier per user. This is for finding friends, etc..

8.3 AuthenticationValues Class Reference

Container for user authentication in [Photon](#). Set `AuthValues` before you connect - all else is handled.

Public Member Functions

- [AuthenticationValues](#) ()
Creates empty auth values without any info.
- [AuthenticationValues](#) (string `userId`)
Creates minimal info about the user. If this is authenticated or not, depends on the set `AuthType`.
- virtual void [SetAuthPostData](#) (string `stringData`)
Sets the data to be passed-on to the auth service via POST.
- virtual void [SetAuthPostData](#) (byte[] `byteData`)
Sets the data to be passed-on to the auth service via POST.
- virtual void [AddAuthParameter](#) (string `key`, string `value`)
Adds a key-value pair to the get-parameters used for Custom Auth.
- override string [ToString](#) ()

Properties

- [CustomAuthenticationType](#) `AuthType` [get, set]
The type of custom authentication provider that should be used. Currently only "Custom" or "None" (turns this off).
- string [AuthGetParameters](#) [get, set]
This string must contain any (http get) parameters expected by the used authentication service. By default, username and token.
- object [AuthPostData](#) [get, set]
Data to be passed-on to the auth service via POST. Default: null (not sent). Either string or byte[] (see setters).
- string [Token](#) [get, set]
After initial authentication, [Photon](#) provides a token for this client / user, which is subsequently used as (cached) validation.
- string [UserId](#) [get, set]
The `UserId` should be a unique identifier per user. This is for finding friends, etc..

8.3.1 Detailed Description

Container for user authentication in [Photon](#). Set `AuthValues` before you connect - all else is handled.

On [Photon](#), user authentication is optional but can be useful in many cases. If you want to `FindFriends`, a unique ID per user is very practical.

There are basically three options for user authentication: None at all, the client sets some `UserId` or you can use some account web-service to authenticate a user (and set the `UserId` server-side).

Custom Authentication lets you verify end-users by some kind of login or token. It sends those values to [Photon](#) which will verify them before granting access or disconnecting the client.

The AuthValues are sent in OpAuthenticate when you connect, so they must be set before you connect. Should you not set any AuthValues, PUN will create them and set the playerName as userId in them. If the AuthValues.userId is null or empty when it's sent to the server, then the [Photon](#) Server assigns a userId!

The [Photon](#) Cloud Dashboard will let you enable this feature and set important server values for it. <https://www.photonengine.com/dashboard>

8.3.2 Constructor & Destructor Documentation

8.3.2.1 AuthenticationValues.AuthenticationValues ()

Creates empty auth values without any info.

8.3.2.2 AuthenticationValues.AuthenticationValues (string *userId*)

Creates minimal info about the user. If this is authenticated or not, depends on the set AuthType.

Parameters

<i>userId</i>	Some UserId to set in Photon .
---------------	--

8.3.3 Member Function Documentation

8.3.3.1 virtual void AuthenticationValues.AddAuthParameter (string *key*, string *value*) [virtual]

Adds a key-value pair to the get-parameters used for Custom Auth.

This method does uri-encoding for you.

Parameters

<i>key</i>	Key for the value to set.
<i>value</i>	Some value relevant for Custom Authentication.

8.3.3.2 virtual void AuthenticationValues.SetAuthPostData (string *stringData*) [virtual]

Sets the data to be passed-on to the auth service via POST.

Parameters

<i>stringData</i>	String data to be used in the body of the POST request. Null or empty string will set AuthPostData to null.
-------------------	---

8.3.3.3 virtual void AuthenticationValues.SetAuthPostData (byte[] *byteData*) [virtual]

Sets the data to be passed-on to the auth service via POST.

Parameters

<i>byteData</i>	Binary token / auth-data to pass on.
-----------------	--------------------------------------

8.3.3.4 override string AuthenticationValues.ToString ()

8.3.4 Property Documentation

8.3.4.1 string AuthenticationValues.AuthGetParameters [get], [set]

This string must contain any (http get) parameters expected by the used authentication service. By default, username and token.

Standard http get parameters are used here and passed on to the service that's defined in the server ([Photon Cloud Dashboard](#)).

8.3.4.2 object AuthenticationValues.AuthPostData [get], [set]

Data to be passed-on to the auth service via POST. Default: null (not sent). Either string or byte[] (see setters).

8.3.4.3 CustomAuthenticationType AuthenticationValues.AuthType [get], [set]

The type of custom authentication provider that should be used. Currently only "Custom" or "None" (turns this off).

8.3.4.4 string AuthenticationValues.Token [get], [set]

After initial authentication, [Photon](#) provides a token for this client / user, which is subsequently used as (cached) validation.

8.3.4.5 string AuthenticationValues.UserId [get], [set]

The UserId should be a unique identifier per user. This is for finding friends, etc..

See remarks of AuthValues for info about how this is set and used.

8.4 ExitGames.Client.Photon.Chat.ChatChannel Class Reference

A channel of communication in [Photon Chat](#), updated by [ChatClient](#) and provided as READ ONLY.

Public Member Functions

- [ChatChannel](#) (string name)
Used internally to create new channels. This does NOT create a channel on the server! Use [ChatClient.Subscribe](#).
- void [Add](#) (string sender, object message)
Used internally to add messages to this channel.
- void [Add](#) (string[] senders, object[] messages)
Used internally to add messages to this channel.
- void [TruncateMessages](#) ()
Reduces the number of locally cached messages in this channel to the MessageLimit (if set).
- void [ClearMessages](#) ()
Clear the local cache of messages currently stored. This frees memory but doesn't affect the server.
- string [ToStringMessages](#) ()
Provides a string-representation of all messages in this channel.

Public Attributes

- readonly string [Name](#)
Name of the channel (used to subscribe and unsubscribe).
- readonly List< string > [Senders](#) = new List<string>()
Senders of messages in chronological order. Senders and Messages refer to each other by index. Senders[x] is the sender of Messages[x].
- readonly List< object > [Messages](#) = new List<object>()
Messages in chronological order. Senders and Messages refer to each other by index. Senders[x] is the sender of Messages[x].
- int [MessageLimit](#)
If greater than 0, this channel will limit the number of messages, that it caches locally.

Properties

- bool [IsPrivate](#) [get, set]
Is this a private 1:1 channel?
- int [MessageCount](#) [get]
Count of messages this client still buffers/knows for this channel.

8.4.1 Detailed Description

A channel of communication in [Photon Chat](#), updated by [ChatClient](#) and provided as READ ONLY.

Contains messages and senders to use (read!) and display by your [GUI](#). Access these by: [ChatClient.PublicChannels](#) [ChatClient.PrivateChannels](#)

8.4.2 Constructor & Destructor Documentation

8.4.2.1 `ExitGames.Client.Photon.Chat.ChatChannel.ChatChannel (string name)`

Used internally to create new channels. This does NOT create a channel on the server! Use [ChatClient.Subscribe](#).

8.4.3 Member Function Documentation

8.4.3.1 `void ExitGames.Client.Photon.Chat.ChatChannel.Add (string sender, object message)`

Used internally to add messages to this channel.

8.4.3.2 `void ExitGames.Client.Photon.Chat.ChatChannel.Add (string[] senders, object[] messages)`

Used internally to add messages to this channel.

8.4.3.3 `void ExitGames.Client.Photon.Chat.ChatChannel.ClearMessages ()`

Clear the local cache of messages currently stored. This frees memory but doesn't affect the server.

8.4.3.4 string ExitGames.Client.Photon.Chat.ChatChannel.ToStringMessages ()

Provides a string-representation of all messages in this channel.

Returns

All known messages in format "Sender: Message", line by line.

8.4.3.5 void ExitGames.Client.Photon.Chat.ChatChannel.TruncateMessages ()

Reduces the number of locally cached messages in this channel to the MessageLimit (if set).

8.4.4 Member Data Documentation

8.4.4.1 int ExitGames.Client.Photon.Chat.ChatChannel.MessageLimit

If greater than 0, this channel will limit the number of messages, that it caches locally.

8.4.4.2 readonly List<object> ExitGames.Client.Photon.Chat.ChatChannel.Messages = new List<object>()

Messages in chronological order. Senders and Messages refer to each other by index. Senders[x] is the sender of Messages[x].

8.4.4.3 readonly string ExitGames.Client.Photon.Chat.ChatChannel.Name

Name of the channel (used to subscribe and unsubscribe).

8.4.4.4 readonly List<string> ExitGames.Client.Photon.Chat.ChatChannel.Senders = new List<string>()

Senders of messages in chronological order. Senders and Messages refer to each other by index. Senders[x] is the sender of Messages[x].

8.4.5 Property Documentation

8.4.5.1 bool ExitGames.Client.Photon.Chat.ChatChannel.IsPrivate [get], [set]

Is this a private 1:1 channel?

8.4.5.2 int ExitGames.Client.Photon.Chat.ChatChannel.MessageCount [get]

Count of messages this client still buffers/knows for this channel.

8.5 ExitGames.Client.Photon.Chat.ChatClient Class Reference

Central class of the [Photon Chat](#) API to connect, handle channels and messages.

Inherits IPhotonPeerListener.

Public Member Functions

- bool [CanChatInChannel](#) (string channelName)
- [ChatClient](#) ([IChatClientListener](#) listener, [ConnectionProtocol](#) protocol=[ConnectionProtocol.Udp](#))
- bool [Connect](#) (string appld, string appVersion, [AuthenticationValues](#) authValues)

Connects this client to the [Photon Chat](#) Cloud service, which will also authenticate the user (and set a UserId).
- void [Service](#) ()

Must be called regularly to keep connection between client and server alive and to process incoming messages.
- void [Disconnect](#) ()
- void [StopThread](#) ()
- bool [Subscribe](#) (string[] channels)

Sends operation to subscribe to a list of channels by name.
- bool [Subscribe](#) (string[] channels, int messagesFromHistory)

Sends operation to subscribe client to channels, optionally fetching a number of messages from the cache.
- bool [Unsubscribe](#) (string[] channels)

Unsubscribes from a list of channels, which stops getting messages from those.
- bool [PublishMessage](#) (string channelName, object message, bool forwardAsWebhook=false)

Sends a message to a public channel which this client subscribed to.
- bool [SendPrivateMessage](#) (string target, object message, bool forwardAsWebhook=false)

Sends a private message to a single target user. Calls [OnPrivateMessage](#) on the receiving client.
- bool [SendPrivateMessage](#) (string target, object message, bool encrypt, bool forwardAsWebhook)

Sends a private message to a single target user. Calls [OnPrivateMessage](#) on the receiving client.
- bool [SetOnlineStatus](#) (int status)

Sets the user's status without changing your status-message.
- bool [SetOnlineStatus](#) (int status, object message)

Sets the user's status without changing your status-message.
- bool [AddFriends](#) (string[] friends)

Adds friends to a list on the [Chat](#) Server which will send you status updates for those.
- bool [RemoveFriends](#) (string[] friends)

Removes the provided entries from the list on the [Chat](#) Server and stops their status updates.
- string [GetPrivateChannelNameByUser](#) (string userName)

Get you the (locally used) channel name for the chat between this client and another user.
- bool [TryGetChannel](#) (string channelName, bool isPrivate, out [ChatChannel](#) channel)

Simplified access to either private or public channels by name.
- bool [TryGetChannel](#) (string channelName, out [ChatChannel](#) channel)

Simplified access to all channels by name. Checks public channels first, then private ones.
- void [SendAcksOnly](#) ()

Public Attributes

- int [MessageLimit](#)

If greater than 0, new channels will limit the number of messages they cache locally.
- readonly Dictionary< string, [ChatChannel](#) > [PublicChannels](#)
- readonly Dictionary< string, [ChatChannel](#) > [PrivateChannels](#)
- [ChatPeer](#) chatPeer = null

Properties

- string [NameServerAddress](#) [get, set]
The address of last connected Name Server.
- string [FrontendAddress](#) [get, set]
The address of the actual chat server assigned from NameServer. Public for read only.
- string [ChatRegion](#) [get, set]
Settable only before you connect! Defaults to "EU".
- [ChatState](#) [State](#) [get, set]
Current state of the [ChatClient](#). Also use [CanChat](#).
- [ChatDisconnectCause](#) [DisconnectedCause](#) [get, set]
- bool [CanChat](#) [get]
- string [AppVersion](#) [get, set]
The version of your client. A new version also creates a new "virtual app" to separate players from older client versions.
- string [AppId](#) [get, set]
The AppID as assigned from the [Photon](#) Cloud. If you host yourself, this is the "regular" [Photon](#) Server Application Name (most likely: "LoadBalancing").
- [AuthenticationValues](#) [AuthValues](#) [get, set]
Settable only before you connect!
- string [UserId](#) [get, set]
The unique ID of a user/person, stored in [AuthValues.UserId](#). Set it before you connect.
- DebugLevel [DebugOut](#) [get, set]
Sets the level (and amount) of debug output provided by the library.

8.5.1 Detailed Description

Central class of the [Photon Chat](#) API to connect, handle channels and messages.

This class must be instantiated with a [IChatClientListener](#) instance to get the callbacks. Integrate it into your game loop by calling [Service](#) regularly. Call [Connect](#) with an [AppId](#) that is setup as [Photon Chat](#) application. Note↔: [Connect](#) covers multiple messages between this client and the servers. A short workflow will connect you to a chat server.

Each [ChatClient](#) resembles a user in chat (set in [Connect](#)). Each user automatically subscribes a channel for incoming private messages and can message any other user privately. Before you publish messages in any non-private channel, that channel must be subscribed.

[PublicChannels](#) is a list of subscribed channels, containing messages and senders. [PrivateChannels](#) contains all incoming and sent private messages.

8.5.2 Constructor & Destructor Documentation

8.5.2.1 `ExitGames.Client.Photon.Chat.ChatClient.ChatClient (IChatClientListener listener, ConnectionProtocol protocol = ConnectionProtocol.Udp)`

8.5.3 Member Function Documentation

8.5.3.1 `bool ExitGames.Client.Photon.Chat.ChatClient.AddFriends (string[] friends)`

Adds friends to a list on the [Chat](#) Server which will send you status updates for those.

[AddFriends](#) and [RemoveFriends](#) enable clients to handle their friend list in the [Photon Chat](#) server. Having users on your friends list gives you access to their current online status (and whatever info your client sets in it).

Each user can set an online status consisting of an integer and an arbitrary (serializable) object. The object can be null, Hashtable, object[] or anything else [Photon](#) can serialize.

The status is published automatically to friends (anyone who set your user ID with AddFriends).

[Photon](#) flushes friends-list when a chat client disconnects, so it has to be set each time. If your community API gives you access to online status already, you could filter and set online friends in AddFriends.

Actual friend relations are not persistent and have to be stored outside of [Photon](#).

Parameters

<i>friends</i>	Array of friend userIDs.
----------------	--------------------------

Returns

If the operation could be sent.

8.5.3.2 `bool ExitGames.Client.Photon.Chat.ChatClient.CanChatInChannel (string channelName)`

8.5.3.3 `bool ExitGames.Client.Photon.Chat.ChatClient.Connect (string appId, string appVersion, AuthenticationValues authValues)`

Connects this client to the [Photon Chat](#) Cloud service, which will also authenticate the user (and set a UserId).

Parameters

<i>appId</i>	Get your Photon Chat AppId from the Dashboard .
<i>appVersion</i>	Any version string you make up. Used to separate users and variants of your clients, which might be incompatible.
<i>authValues</i>	Values for authentication. You can leave this null, if you set a UserId before. If you set authValues, they will override any UserId set before.

Returns

8.5.3.4 `void ExitGames.Client.Photon.Chat.ChatClient.Disconnect ()`

8.5.3.5 `string ExitGames.Client.Photon.Chat.ChatClient.GetPrivateChannelNameByUser (string userName)`

Get you the (locally used) channel name for the chat between this client and another user.

Parameters

<i>userName</i>	Remote user's name or UserId.
-----------------	-------------------------------

Returns

The (locally used) channel name for a private channel.

8.5.3.6 `bool ExitGames.Client.Photon.Chat.ChatClient.PublishMessage (string channelName, object message, bool forwardAsWebhook = false)`

Sends a message to a public channel which this client subscribed to.

Before you publish to a channel, you have to subscribe it. Everyone in that channel will get the message.

Parameters

<i>channelName</i>	Name of the channel to publish to.
<i>message</i>	Your message (string or any serializable data).
<i>forwardAsWebhook</i>	Optionally, public messages can be forwarded as webhooks. Configure webhooks for your Chat app to use this.

Returns

False if the client is not yet ready to send messages.

8.5.3.7 bool ExitGames.Client.Photon.Chat.ChatClient.RemoveFriends (string[] friends)

Removes the provided entries from the list on the [Chat](#) Server and stops their status updates.

[Photon](#) flushes friends-list when a chat client disconnects. Unless you want to remove individual entries, you don't have to RemoveFriends.

AddFriends and RemoveFriends enable clients to handle their friend list in the [Photon Chat](#) server. Having users on your friends list gives you access to their current online status (and whatever info your client sets in it).

Each user can set an online status consisting of an integer and an arbitrary (serializable) object. The object can be null, Hashtable, object[] or anything else [Photon](#) can serialize.

The status is published automatically to friends (anyone who set your user ID with AddFriends).

[Photon](#) flushes friends-list when a chat client disconnects, so it has to be set each time. If your community API gives you access to online status already, you could filter and set online friends in AddFriends.

Actual friend relations are not persistent and have to be stored outside of [Photon](#).

AddFriends and RemoveFriends enable clients to handle their friend list in the [Photon Chat](#) server. Having users on your friends list gives you access to their current online status (and whatever info your client sets in it).

Each user can set an online status consisting of an integer and an arbitrary (serializable) object. The object can be null, Hashtable, object[] or anything else [Photon](#) can serialize.

The status is published automatically to friends (anyone who set your user ID with AddFriends).

Actual friend relations are not persistent and have to be stored outside of [Photon](#).

Parameters

<i>friends</i>	Array of friend userIDs.
----------------	--------------------------

Returns

If the operation could be sent.

8.5.3.8 void ExitGames.Client.Photon.Chat.ChatClient.SendAcksOnly ()

8.5.3.9 bool ExitGames.Client.Photon.Chat.ChatClient.SendPrivateMessage (string target, object message, bool forwardAsWebhook = false)

Sends a private message to a single target user. Calls OnPrivateMessage on the receiving client.

Parameters

<i>target</i>	Username to send this message to.
<i>message</i>	The message you want to send. Can be a simple string or anything serializable.
<i>forwardAsWebhook</i>	Optionally, private messages can be forwarded as webhooks. Configure webhooks for your Chat app to use this.

Returns

True if this clients can send the message to the server.

8.5.3.10 `bool ExitGames.Client.Photon.Chat.ChatClient.SendPrivateMessage (string target, object message, bool encrypt, bool forwardAsWebhook)`

Sends a private message to a single target user. Calls OnPrivateMessage on the receiving client.

Parameters

<i>target</i>	Username to send this message to.
<i>message</i>	The message you want to send. Can be a simple string or anything serializable.
<i>encrypt</i>	Optionally, private messages can be encrypted. Encryption is not end-to-end as the server decrypts the message.
<i>forwardAsWebhook</i>	Optionally, private messages can be forwarded as webhooks. Configure webhooks for your Chat app to use this.

Returns

True if this clients can send the message to the server.

8.5.3.11 `void ExitGames.Client.Photon.Chat.ChatClient.Service ()`

Must be called regularly to keep connection between client and server alive and to process incoming messages.

This method limits the effort it does automatically using the private variable msDeltaForServiceCalls. That value is lower for connect and multiplied by 4 when chat-server connection is ready.

8.5.3.12 `bool ExitGames.Client.Photon.Chat.ChatClient.SetOnlineStatus (int status)`

Sets the user's status without changing your status-message.

The predefined status values can be found in class [ChatUserStatus](#). State [ChatUserStatus.Invisible](#) will make you offline for everyone and send no message.

You can set custom values in the status integer. Aside from the pre-configured ones, all states will be considered visible and online. Else, no one would see the custom state.

This overload does not change the set message.

Parameters

<i>status</i>	Predefined states are in class ChatUserStatus . Other values can be used at will.
---------------	---

Returns

True if the operation gets called on the server.

8.5.3.13 `bool ExitGames.Client.Photon.Chat.ChatClient.SetOnlineStatus (int status, object message)`

Sets the user's status without changing your status-message.

The predefined status values can be found in class [ChatUserStatus](#). State [ChatUserStatus.Invisible](#) will make you offline for everyone and send no message.

You can set custom values in the status integer. Aside from the pre-configured ones, all states will be considered visible and online. Else, no one would see the custom state.

The message object can be anything that [Photon](#) can serialize, including (but not limited to) Hashtable, object[] and string. This value is defined by your own conventions.

Parameters

<i>status</i>	Predefined states are in class ChatUserStatus . Other values can be used at will.
<i>message</i>	Also sets a status-message which your friends can get.

Returns

True if the operation gets called on the server.

8.5.3.14 `void ExitGames.Client.Photon.Chat.ChatClient.StopThread ()`**8.5.3.15** `bool ExitGames.Client.Photon.Chat.ChatClient.Subscribe (string[] channels)`

Sends operation to subscribe to a list of channels by name.

Parameters

<i>channels</i>	List of channels to subscribe to. Avoid null or empty values.
-----------------	---

Returns

If the operation could be sent at all (Example: Fails if not connected to [Chat Server](#)).

8.5.3.16 `bool ExitGames.Client.Photon.Chat.ChatClient.Subscribe (string[] channels, int messagesFromHistory)`

Sends operation to subscribe client to channels, optionally fetching a number of messages from the cache.

Subscribes channels will forward new messages to this user. Use `PublishMessage` to do so. The messages cache is limited but can be useful to get into ongoing conversations, if that's needed.

Parameters

<i>channels</i>	List of channels to subscribe to. Avoid null or empty values.
<i>messagesFromHistory</i>	0: no history. 1 and higher: number of messages in history. -1: all available history.

Returns

If the operation could be sent at all (Example: Fails if not connected to [Chat Server](#)).

8.5.3.17 `bool ExitGames.Client.Photon.Chat.ChatClient.TryGetChannel (string channelName, bool isPrivate, out ChatChannel channel)`

Simplified access to either private or public channels by name.

Parameters

<i>channelName</i>	Name of the channel to get. For private channels, the channel-name is composed of both user's names.
<i>isPrivate</i>	Define if you expect a private or public channel.
<i>channel</i>	Out parameter gives you the found channel, if any.

Returns

True if the channel was found.

8.5.3.18 `bool ExitGames.Client.Photon.Chat.ChatClient.TryGetChannel (string channelName, out ChatChannel channel)`

Simplified access to all channels by name. Checks public channels first, then private ones.

Parameters

<i>channelName</i>	Name of the channel to get.
<i>channel</i>	Out parameter gives you the found channel, if any.

Returns

True if the channel was found.

8.5.3.19 `bool ExitGames.Client.Photon.Chat.ChatClient.Unsubscribe (string[] channels)`

Unsubscribes from a list of channels, which stops getting messages from those.

The client will remove these channels from the PublicChannels dictionary once the server sent a response to this request.

The request will be sent to the server and [IChatClientListener.OnUnsubscribed](#) gets called when the server actually removed the channel subscriptions.

Unsubscribe will fail if you include null or empty channel names.

Parameters

<i>channels</i>	Names of channels to unsubscribe.
-----------------	-----------------------------------

Returns

False, if not connected to a chat server.

8.5.4 Member Data Documentation

8.5.4.1 `ChatPeer ExitGames.Client.Photon.Chat.ChatClient.chatPeer = null`

8.5.4.2 `int ExitGames.Client.Photon.Chat.ChatClient.MessageLimit`

If greater than 0, new channels will limit the number of messages they cache locally.

This can be useful to limit the amount of memory used by chats. You can set a MessageLimit per channel but this value gets applied to new ones.

Note: Changing this value, does not affect ChatChannels that are already in use!

8.5.4.3 readonly Dictionary<string, ChatChannel> ExitGames.Client.Photon.Chat.ChatClient.PrivateChannels

8.5.4.4 readonly Dictionary<string, ChatChannel> ExitGames.Client.Photon.Chat.ChatClient.PublicChannels

8.5.5 Property Documentation

8.5.5.1 string ExitGames.Client.Photon.Chat.ChatClient.AppId [get], [set]

The AppID as assigned from the [Photon](#) Cloud. If you host yourself, this is the "regular" [Photon](#) Server Application Name (most likely: "LoadBalancing").

8.5.5.2 string ExitGames.Client.Photon.Chat.ChatClient.AppVersion [get], [set]

The version of your client. A new version also creates a new "virtual app" to separate players from older client versions.

8.5.5.3 AuthenticationValues ExitGames.Client.Photon.Chat.ChatClient.AuthValues [get], [set]

Settable only before you connect!

8.5.5.4 bool ExitGames.Client.Photon.Chat.ChatClient.CanChat [get]

8.5.5.5 string ExitGames.Client.Photon.Chat.ChatClient.ChatRegion [get], [set]

Settable only before you connect! Defaults to "EU".

8.5.5.6 DebugLevel ExitGames.Client.Photon.Chat.ChatClient.DebugOut [get], [set]

Sets the level (and amount) of debug output provided by the library.

This affects the callbacks to [IChatClientListener.DebugReturn](#). Default Level: Error.

8.5.5.7 ChatDisconnectCause ExitGames.Client.Photon.Chat.ChatClient.DisconnectedCause [get], [set]

8.5.5.8 string ExitGames.Client.Photon.Chat.ChatClient.FrontendAddress [get], [set]

The address of the actual chat server assigned from NameServer. Public for read only.

8.5.5.9 string ExitGames.Client.Photon.Chat.ChatClient.NameServerAddress [get], [set]

The address of last connected Name Server.

8.5.5.10 ChatState ExitGames.Client.Photon.Chat.ChatClient.State [get], [set]

Current state of the [ChatClient](#). Also use CanChat.

8.5.5.11 string ExitGames.Client.Photon.Chat.ChatClient.UserId [get], [set]

The unique ID of a user/person, stored in AuthValues.UserId. Set it before you connect.

This value wraps AuthValues.UserId. It's not a nickname and we assume users with the same userID are the same person.

8.6 ExitGames.Client.Photon.Chat.ChatEventCode Class Reference

Wraps up internally used constants in [Photon Chat](#) events. You don't have to use them directly usually.

Public Attributes

- const byte [ChatMessages](#) = 0
- const byte [Users](#) = 1
- const byte [PrivateMessage](#) = 2
- const byte [FriendsList](#) = 3
- const byte [StatusUpdate](#) = 4
- const byte [Subscribe](#) = 5
- const byte [Unsubscribe](#) = 6

8.6.1 Detailed Description

Wraps up internally used constants in [Photon Chat](#) events. You don't have to use them directly usually.

8.6.2 Member Data Documentation

8.6.2.1 const byte ExitGames.Client.Photon.Chat.ChatEventCode.ChatMessages = 0

8.6.2.2 const byte ExitGames.Client.Photon.Chat.ChatEventCode.FriendsList = 3

8.6.2.3 const byte ExitGames.Client.Photon.Chat.ChatEventCode.PrivateMessage = 2

8.6.2.4 const byte ExitGames.Client.Photon.Chat.ChatEventCode.StatusUpdate = 4

8.6.2.5 const byte ExitGames.Client.Photon.Chat.ChatEventCode.Subscribe = 5

8.6.2.6 const byte ExitGames.Client.Photon.Chat.ChatEventCode.Unsubscribe = 6

8.6.2.7 const byte ExitGames.Client.Photon.Chat.ChatEventCode.Users = 1

8.7 ExitGames.Client.Photon.Chat.ChatOperationCode Class Reference

Wraps up codes for operations used internally in [Photon Chat](#). You don't have to use them directly usually.

Public Attributes

- const byte [Authenticate](#) = 230
(230) Operation Authenticate.
- const byte [Subscribe](#) = 0
(0) Operation to subscribe to chat channels.
- const byte [Unsubscribe](#) = 1
(1) Operation to unsubscribe from chat channels.
- const byte [Publish](#) = 2
(2) Operation to publish a message in a chat channel.
- const byte [SendPrivate](#) = 3
(3) Operation to send a private message to some other user.
- const byte [ChannelHistory](#) = 4

- (4) Not used yet.*
- const byte [UpdateStatus](#) = 5
 - (5) Set your (client's) status.*
- const byte [AddFriends](#) = 6
 - (6) Add friends the list of friends that should update you of their status.*
- const byte [RemoveFriends](#) = 7
 - (7) Remove friends from list of friends that should update you of their status.*

8.7.1 Detailed Description

Wraps up codes for operations used internally in [Photon Chat](#). You don't have to use them directly usually.

8.7.2 Member Data Documentation

8.7.2.1 const byte ExitGames.Client.Photon.Chat.ChatOperationCode.AddFriends = 6

(6) Add friends the list of friends that should update you of their status.

8.7.2.2 const byte ExitGames.Client.Photon.Chat.ChatOperationCode.Authenticate = 230

(230) Operation Authenticate.

8.7.2.3 const byte ExitGames.Client.Photon.Chat.ChatOperationCode.ChannelHistory = 4

(4) Not used yet.

8.7.2.4 const byte ExitGames.Client.Photon.Chat.ChatOperationCode.Publish = 2

(2) Operation to publish a message in a chat channel.

8.7.2.5 const byte ExitGames.Client.Photon.Chat.ChatOperationCode.RemoveFriends = 7

(7) Remove friends from list of friends that should update you of their status.

8.7.2.6 const byte ExitGames.Client.Photon.Chat.ChatOperationCode.SendPrivate = 3

(3) Operation to send a private message to some other user.

8.7.2.7 const byte ExitGames.Client.Photon.Chat.ChatOperationCode.Subscribe = 0

(0) Operation to subscribe to chat channels.

8.7.2.8 const byte ExitGames.Client.Photon.Chat.ChatOperationCode.Unsubscribe = 1

(1) Operation to unsubscribe from chat channels.

8.7.2.9 const byte ExitGames.Client.Photon.Chat.ChatOperationCode.UpdateStatus = 5

(5) Set your (client's) status.

8.8 ExitGames.Client.Photon.Chat.ChatParameterCode Class Reference

Wraps up codes for parameters (in operations and events) used internally in [Photon Chat](#). You don't have to use them directly usually.

Public Attributes

- const byte [Channels](#) = 0
(0) Array of chat channels.
- const byte [Channel](#) = 1
(1) Name of a single chat channel.
- const byte [Messages](#) = 2
(2) Array of chat messages.
- const byte [Message](#) = 3
(3) A single chat message.
- const byte [Senders](#) = 4
(4) Array of names of the users who sent the array of chat messages.
- const byte [Sender](#) = 5
(5) Name of a the user who sent a chat message.
- const byte [ChannelUserCount](#) = 6
(6) Not used.
- const byte [UserId](#) = 225
(225) Name of user to send a (private) message to.
- const byte [MsgId](#) = 8
(8) Id of a message.
- const byte [MsgIds](#) = 9
(9) Not used.
- const byte [Secret](#) = 221
(221) Secret token to identify an authorized user.
- const byte [SubscribeResults](#) = 15
(15) Subscribe operation result parameter. A bool[] with result per channel.
- const byte [Status](#) = 10
(10) Status
- const byte [Friends](#) = 11
(11) Friends
- const byte [SkipMessage](#) = 12
(12) SkipMessage is used in SetOnlineStatus and if true, the message is not being broadcast.
- const byte [HistoryLength](#) = 14
(14) Number of message to fetch from history. 0: no history. 1 and higher: number of messages in history. -1: all history.
- const byte [WebFlags](#) = 21
(21) WebFlags object for changing behaviour of webhooks from client.

8.8.1 Detailed Description

Wraps up codes for parameters (in operations and events) used internally in [Photon Chat](#). You don't have to use them directly usually.

8.8.2 Member Data Documentation

8.8.2.1 `const byte ExitGames.Client.Photon.Chat.ChatParameterCode.Channel = 1`

(1) Name of a single chat channel.

8.8.2.2 `const byte ExitGames.Client.Photon.Chat.ChatParameterCode.Channels = 0`

(0) Array of chat channels.

8.8.2.3 `const byte ExitGames.Client.Photon.Chat.ChatParameterCode.ChannelUserCount = 6`

(6) Not used.

8.8.2.4 `const byte ExitGames.Client.Photon.Chat.ChatParameterCode.Friends = 11`

(11) Friends

8.8.2.5 `const byte ExitGames.Client.Photon.Chat.ChatParameterCode.HistoryLength = 14`

(14) Number of message to fetch from history. 0: no history. 1 and higher: number of messages in history. -1: all history.

8.8.2.6 `const byte ExitGames.Client.Photon.Chat.ChatParameterCode.Message = 3`

(3) A single chat message.

8.8.2.7 `const byte ExitGames.Client.Photon.Chat.ChatParameterCode.Messages = 2`

(2) Array of chat messages.

8.8.2.8 `const byte ExitGames.Client.Photon.Chat.ChatParameterCode.MsgId = 8`

(8) Id of a message.

8.8.2.9 `const byte ExitGames.Client.Photon.Chat.ChatParameterCode.MsgIds = 9`

(9) Not used.

8.8.2.10 `const byte ExitGames.Client.Photon.Chat.ChatParameterCode.Secret = 221`

(221) Secret token to identify an authorized user.

The code is used in LoadBalancing and copied over here.

8.8.2.11 `const byte ExitGames.Client.Photon.Chat.ChatParameterCode.Sender = 5`

(5) Name of a the user who sent a chat message.

8.8.2.12 `const byte ExitGames.Client.Photon.Chat.ChatParameterCode.Senders = 4`

(4) Array of names of the users who sent the array of chat messages.

8.8.2.13 `const byte ExitGames.Client.Photon.Chat.ChatParameterCode.SkipMessage = 12`

(12) SkipMessage is used in SetOnlineStatus and if true, the message is not being broadcast.

8.8.2.14 `const byte ExitGames.Client.Photon.Chat.ChatParameterCode.Status = 10`

(10) Status

8.8.2.15 `const byte ExitGames.Client.Photon.Chat.ChatParameterCode.SubscribeResults = 15`

(15) Subscribe operation result parameter. A bool[] with result per channel.

8.8.2.16 `const byte ExitGames.Client.Photon.Chat.ChatParameterCode.UserId = 225`

(225) Name of user to send a (private) message to.

The code is used in LoadBalancing and copied over here.

8.8.2.17 `const byte ExitGames.Client.Photon.Chat.ChatParameterCode.WebFlags = 21`

(21) WebFlags object for changing behaviour of webhooks from client.

8.9 ExitGames.Client.Photon.Chat.ChatPeer Class Reference

Provides basic operations of the [Photon Chat](#) server. This internal class is used by public [ChatClient](#).

Inherits PhotonPeer.

Public Member Functions

- [ChatPeer](#) (IPhotonPeerListener listener, ConnectionProtocol protocol)
- bool [Connect](#) ()
- bool [AuthenticateOnNameServer](#) (string appld, string appVersion, string region, [AuthenticationValues](#) auth←Values)

Public Attributes

- const string [NameServerHost](#) = "ns.exitgames.com"
Name Server Host Name for [Photon Cloud](#). Without port and without any prefix.
- const string [NameServerHttp](#) = "http://ns.exitgamescloud.com:80/photon/n"
Name Server for HTTP connections to the [Photon Cloud](#). Includes prefix and port.

Properties

- string [NameServerAddress](#) [get]
Name Server Address for [Photon Cloud](#) (based on current protocol). You can use the default values and usually won't have to set this value.

8.9.1 Detailed Description

Provides basic operations of the [Photon Chat](#) server. This internal class is used by public [ChatClient](#).

8.9.2 Constructor & Destructor Documentation

8.9.2.1 `ExitGames.Client.Photon.Chat.ChatPeer.ChatPeer (IPhotonPeerListener listener, ConnectionProtocol protocol)`

8.9.3 Member Function Documentation

8.9.3.1 `bool ExitGames.Client.Photon.Chat.ChatPeer.AuthenticateOnNameServer (string appld, string appVersion, string region, AuthenticationValues authValues)`

8.9.3.2 `bool ExitGames.Client.Photon.Chat.ChatPeer.Connect ()`

8.9.4 Member Data Documentation

8.9.4.1 `const string ExitGames.Client.Photon.Chat.ChatPeer.NameServerHost = "ns.exitgames.com"`

Name Server Host Name for [Photon](#) Cloud. Without port and without any prefix.

8.9.4.2 `const string ExitGames.Client.Photon.Chat.ChatPeer.NameServerHttp = "http://ns.exitgamescloud.com:80/photon/n"`

Name Server for HTTP connections to the [Photon](#) Cloud. Includes prefix and port.

8.9.5 Property Documentation

8.9.5.1 `string ExitGames.Client.Photon.Chat.ChatPeer.NameServerAddress` `[get]`

Name Server Address for [Photon](#) Cloud (based on current protocol). You can use the default values and usually won't have to set this value.

8.10 ExitGames.Client.Photon.Chat.ChatUserStatus Class Reference

Contains commonly used status values for SetOnlineStatus. You can define your own.

Public Attributes

- `const int Offline = 0`
(0) Offline.
- `const int Invisible = 1`
(1) Be invisible to everyone. Sends no message.
- `const int Online = 2`
(2) Online and available.
- `const int Away = 3`
(3) Online but not available.
- `const int DND = 4`
(4) Do not disturb.
- `const int LFG = 5`
(5) Looking For Game/Group. Could be used when you want to be invited or do matchmaking.

- const int `Playing` = 6
(6) Could be used when in a room, playing.

8.10.1 Detailed Description

Contains commonly used status values for `SetOnlineStatus`. You can define your own.

While "online" (value 2 and up), the status message will be sent to anyone who has you on his friend list.

Define custom online status values as you like with these rules: 0: Means "offline". It will be used when you are not connected. In this status, there is no status message. 1: Means "invisible" and is sent to friends as "offline". They see status 0, no message but you can chat. 2: And any higher value will be treated as "online". Status can be set.

8.10.2 Member Data Documentation

8.10.2.1 `const int ExitGames.Client.Photon.Chat.ChatUserStatus.Away = 3`

(3) Online but not available.

8.10.2.2 `const int ExitGames.Client.Photon.Chat.ChatUserStatus.DND = 4`

(4) Do not disturb.

8.10.2.3 `const int ExitGames.Client.Photon.Chat.ChatUserStatus.Invisible = 1`

(1) Be invisible to everyone. Sends no message.

8.10.2.4 `const int ExitGames.Client.Photon.Chat.ChatUserStatus.LFG = 5`

(5) Looking For Game/Group. Could be used when you want to be invited or do matchmaking.

8.10.2.5 `const int ExitGames.Client.Photon.Chat.ChatUserStatus.Offline = 0`

(0) Offline.

8.10.2.6 `const int ExitGames.Client.Photon.Chat.ChatUserStatus.Online = 2`

(2) Online and available.

8.10.2.7 `const int ExitGames.Client.Photon.Chat.ChatUserStatus.Playing = 6`

(6) Could be used when in a room, playing.

8.11 EncryptionDataParameters Class Reference

Public Attributes

- const byte `Mode` = 0
Key for encryption mode
- const byte `Secret1` = 1

- Key for first secret*
 • const byte [Secret2](#) = 2
Key for second secret

8.11.1 Member Data Documentation

8.11.1.1 const byte EncryptionDataParameters.Mode = 0

Key for encryption mode

8.11.1.2 const byte EncryptionDataParameters.Secret1 = 1

Key for first secret

8.11.1.3 const byte EncryptionDataParameters.Secret2 = 2

Key for second secret

8.12 ExitGames.Client.Photon.Chat.ErrorCode Class Reference

[ErrorCode](#) defines the default codes associated with [Photon](#) client/server communication.

Public Attributes

- const int [Ok](#) = 0
(0) is always "OK", anything else an error or specific situation.
- const int [OperationNotAllowedInCurrentState](#) = -3
(-3) Operation can't be executed yet (e.g. OpJoin can't be called before being authenticated, RaiseEvent cant be used before getting into a room).
- const int [InvalidOperationCode](#) = -2
(-2) The operation you called is not implemented on the server (application) you connect to. Make sure you run the fitting applications.
- const int [InternalServerError](#) = -1
(-1) Something went wrong in the server. Try to reproduce and contact Exit Games.
- const int [InvalidAuthentication](#) = 0x7FFF
(32767) Authentication failed. Possible cause: Appld is unknown to [Photon](#) (in cloud service).
- const int [GameIdAlreadyExists](#) = 0x7FFF - 1
(32766) GameId (name) already in use (can't create another). Change name.
- const int [GameFull](#) = 0x7FFF - 2
(32765) Game is full. This rarely happens when some player joined the room before your join completed.
- const int [GameClosed](#) = 0x7FFF - 3
(32764) Game is closed and can't be joined. Join another game.
- const int [ServerFull](#) = 0x7FFF - 5
(32762) Not in use currently.
- const int [UserBlocked](#) = 0x7FFF - 6
(32761) Not in use currently.
- const int [NoRandomMatchFound](#) = 0x7FFF - 7
(32760) Random matchmaking only succeeds if a room exists thats neither closed nor full. Repeat in a few seconds or create a new room.
- const int [GameDoesNotExist](#) = 0x7FFF - 9

- (32758) Join can fail if the room (name) is not existing (anymore). This can happen when players leave while you join.
- `const int MaxCcuReached = 0x7FFF - 10`
(32757) Authorization on the [Photon](#) Cloud failed because the concurrent users (CCU) limit of the app's subscription is reached.
- `const int InvalidRegion = 0x7FFF - 11`
(32756) Authorization on the [Photon](#) Cloud failed because the app's subscription does not allow to use a particular region's server.
- `const int CustomAuthenticationFailed = 0x7FFF - 12`
(32755) Custom Authentication of the user failed due to setup reasons (see Cloud Dashboard) or the provided user data (like username or token). Check error message for details.

8.12.1 Detailed Description

[ErrorCode](#) defines the default codes associated with [Photon](#) client/server communication.

8.12.2 Member Data Documentation

8.12.2.1 `const int ExitGames.Client.Photon.Chat.ErrorCode.CustomAuthenticationFailed = 0x7FFF - 12`

(32755) Custom Authentication of the user failed due to setup reasons (see Cloud Dashboard) or the provided user data (like username or token). Check error message for details.

8.12.2.2 `const int ExitGames.Client.Photon.Chat.ErrorCode.GameClosed = 0x7FFF - 3`

(32764) Game is closed and can't be joined. Join another game.

8.12.2.3 `const int ExitGames.Client.Photon.Chat.ErrorCode.GameDoesNotExist = 0x7FFF - 9`

(32758) Join can fail if the room (name) is not existing (anymore). This can happen when players leave while you join.

8.12.2.4 `const int ExitGames.Client.Photon.Chat.ErrorCode.GameFull = 0x7FFF - 2`

(32765) Game is full. This rarely happens when some player joined the room before your join completed.

8.12.2.5 `const int ExitGames.Client.Photon.Chat.ErrorCode.GameIdAlreadyExists = 0x7FFF - 1`

(32766) GameId (name) already in use (can't create another). Change name.

8.12.2.6 `const int ExitGames.Client.Photon.Chat.ErrorCode.InternalServerError = -1`

(-1) Something went wrong in the server. Try to reproduce and contact Exit Games.

8.12.2.7 `const int ExitGames.Client.Photon.Chat.ErrorCode.InvalidAuthentication = 0x7FFF`

(32767) Authentication failed. Possible cause: AppId is unknown to [Photon](#) (in cloud service).

8.12.2.8 `const int ExitGames.Client.Photon.Chat.ErrorCode.InvalidOperationCode = -2`

(-2) The operation you called is not implemented on the server (application) you connect to. Make sure you run the fitting applications.

8.12.2.9 `const int ExitGames.Client.Photon.Chat.ErrorCode.InvalidRegion = 0x7FFF - 11`

(32756) Authorization on the [Photon](#) Cloud failed because the app's subscription does not allow to use a particular region's server.

Some subscription plans for the [Photon](#) Cloud are region-bound. Servers of other regions can't be used then. Check your master server address and compare it with your [Photon](#) Cloud Dashboard's info. <https://cloud.photonengine.com/dashboard>

OpAuthorize is part of connection workflow but only on the [Photon](#) Cloud, this error can happen. Self-hosted [Photon](#) servers with a CCU limited license won't let a client connect at all.

8.12.2.10 `const int ExitGames.Client.Photon.Chat.ErrorCode.MaxCcuReached = 0x7FFF - 10`

(32757) Authorization on the [Photon](#) Cloud failed because the concurrent users (CCU) limit of the app's subscription is reached.

Unless you have a plan with "CCU Burst", clients might fail the authentication step during connect. Affected client are unable to call operations. Please note that players who end a game and return to the master server will disconnect and re-connect, which means that they just played and are rejected in the next minute / re-connect. This is a temporary measure. Once the CCU is below the limit, players will be able to connect and play again.

OpAuthorize is part of connection workflow but only on the [Photon](#) Cloud, this error can happen. Self-hosted [Photon](#) servers with a CCU limited license won't let a client connect at all.

8.12.2.11 `const int ExitGames.Client.Photon.Chat.ErrorCode.NoRandomMatchFound = 0x7FFF - 7`

(32760) Random matchmaking only succeeds if a room exists that's neither closed nor full. Repeat in a few seconds or create a new room.

8.12.2.12 `const int ExitGames.Client.Photon.Chat.ErrorCode.Ok = 0`

(0) is always "OK", anything else an error or specific situation.

8.12.2.13 `const int ExitGames.Client.Photon.Chat.ErrorCode.OperationNotAllowedInCurrentState = -3`

(-3) Operation can't be executed yet (e.g. OpJoin can't be called before being authenticated, RaiseEvent can't be used before getting into a room).

Before you call any operations on the Cloud servers, the automated client workflow must complete its authorization. In PUN, wait until State is: JoinedLobby (with AutoJoinLobby = true) or ConnectedToMaster (AutoJoinLobby = false)

8.12.2.14 `const int ExitGames.Client.Photon.Chat.ErrorCode.ServerFull = 0x7FFF - 5`

(32762) Not in use currently.

8.12.2.15 `const int ExitGames.Client.Photon.Chat.ErrorCode.UserBlocked = 0x7FFF - 6`

(32761) Not in use currently.

8.13 ErrorCode Class Reference

[ErrorCode](#) defines the default codes associated with [Photon](#) client/server communication.

Public Attributes

- const int [Ok](#) = 0
(0) is always "OK", anything else an error or specific situation.
- const int [OperationNotAllowedInCurrentState](#) = -3
(-3) Operation can't be executed yet (e.g. [OpJoin](#) can't be called before being authenticated, [RaiseEvent](#) can't be used before getting into a room).
- const int [InvalidOperationCode](#) = -2
(-2) The operation you called is not implemented on the server (application) you connect to. Make sure you run the fitting applications.
- const int [InvalidOperation](#) = -2
(-2) The operation you called could not be executed on the server.
- const int [InternalServerError](#) = -1
(-1) Something went wrong in the server. Try to reproduce and contact Exit Games.
- const int [InvalidAuthentication](#) = 0x7FFF
(32767) Authentication failed. Possible cause: Appld is unknown to [Photon](#) (in cloud service).
- const int [GameldAlreadyExists](#) = 0x7FFF - 1
(32766) Gameld (name) already in use (can't create another). Change name.
- const int [GameFull](#) = 0x7FFF - 2
(32765) Game is full. This rarely happens when some player joined the room before your join completed.
- const int [GameClosed](#) = 0x7FFF - 3
(32764) Game is closed and can't be joined. Join another game.
- const int [AlreadyMatched](#) = 0x7FFF - 4
- const int [ServerFull](#) = 0x7FFF - 5
(32762) Not in use currently.
- const int [UserBlocked](#) = 0x7FFF - 6
(32761) Not in use currently.
- const int [NoRandomMatchFound](#) = 0x7FFF - 7
(32760) Random matchmaking only succeeds if a room exists thats neither closed nor full. Repeat in a few seconds or create a new room.
- const int [GameDoesNotExist](#) = 0x7FFF - 9
(32758) Join can fail if the room (name) is not existing (anymore). This can happen when players leave while you join.
- const int [MaxCcuReached](#) = 0x7FFF - 10
(32757) Authorization on the [Photon](#) Cloud failed becaus the concurrent users (CCU) limit of the app's subscription is reached.
- const int [InvalidRegion](#) = 0x7FFF - 11
(32756) Authorization on the [Photon](#) Cloud failed because the app's subscription does not allow to use a particular region's server.
- const int [CustomAuthenticationFailed](#) = 0x7FFF - 12
(32755) Custom Authentication of the user failed due to setup reasons (see Cloud Dashboard) or the provided user data (like username or token). Check error message for details.
- const int [AuthenticationTicketExpired](#) = 0x7FFF1
(32753) The Authentication ticket expired. Usually, this is refreshed behind the scenes. Connect (and authorize) again.
- const int [PluginReportedError](#) = 0x7FFF - 15
*(32752) A server-side plugin (or webhook) failed to execute and reported an error. Check the [OperationResponse](#).↔
[DebugMessage](#).*
- const int [PluginMismatch](#) = 0x7FFF - 16
(32751) CreateRoom/JoinRoom/Join operation fails if expected plugin does not correspond to loaded one.
- const int [JoinFailedPeerAlreadyJoined](#) = 32750
(32750) for join requests. Indicates the current peer already called join and is joined to the room.
- const int [JoinFailedFoundInactiveJoiner](#) = 32749

- (32749) for join requests. Indicates the list of InactiveActors already contains an actor with the requested ActorNr or UserId.*
- const int [JoinFailedWithRejoinerNotFound](#) = 32748
(32748) for join requests. Indicates the list of Actors (active and inactive) did not contain an actor with the requested ActorNr or UserId.
- const int [JoinFailedFoundExcludedUserId](#) = 32747
(32747) for join requests. Note: for future use - Indicates the requested UserId was found in the ExcludedList.
- const int [JoinFailedFoundActiveJoiner](#) = 32746
(32746) for join requests. Indicates the list of ActiveActors already contains an actor with the requested ActorNr or UserId.
- const int [HttpLimitReached](#) = 32745
(32745) for SetProperty and RaiseEvent (if flag HttpForward is true) requests. Indicates the maximum allowed http requests per minute was reached.
- const int [ExternalHttpCallFailed](#) = 32744
(32744) for WebRpc requests. Indicates the the call to the external service failed.
- const int [SlotError](#) = 32742
(32742) Server error during matchmaking with slot reservation. E.g. the reserved slots can not exceed MaxPlayers.
- const int [InvalidEncryptionParameters](#) = 32741
(32741) Server will react with this error if invalid encryption parameters provided by token

8.13.1 Detailed Description

[ErrorCode](#) defines the default codes associated with [Photon](#) client/server communication.

8.13.2 Member Data Documentation

8.13.2.1 const int [ErrorCode.AlreadyMatched](#) = 0x7FFF - 4

8.13.2.2 const int [ErrorCode.AuthenticationTicketExpired](#) = 0x7FF1

(32753) The Authentication ticket expired. Usually, this is refreshed behind the scenes. Connect (and authorize) again.

8.13.2.3 const int [ErrorCode.CustomAuthenticationFailed](#) = 0x7FFF - 12

(32755) Custom Authentication of the user failed due to setup reasons (see Cloud Dashboard) or the provided user data (like username or token). Check error message for details.

8.13.2.4 const int [ErrorCode.ExternalHttpCallFailed](#) = 32744

(32744) for WebRpc requests. Indicates the the call to the external service failed.

8.13.2.5 const int [ErrorCode.GameClosed](#) = 0x7FFF - 3

(32764) Game is closed and can't be joined. Join another game.

8.13.2.6 const int [ErrorCode.GameDoesNotExist](#) = 0x7FFF - 9

(32758) Join can fail if the room (name) is not existing (anymore). This can happen when players leave while you join.

8.13.2.7 `const int ErrorCode.GameFull = 0x7FFF - 2`

(32765) Game is full. This rarely happens when some player joined the room before your join completed.

8.13.2.8 `const int ErrorCode.GameIdAlreadyExists = 0x7FFF - 1`

(32766) GameId (name) already in use (can't create another). Change name.

8.13.2.9 `const int ErrorCode.HttpLimitReached = 32745`

(32745) for SetProperty and RaiseEvent (if flag HttpForward is true) requests. Indicates the maximum allowed http requests per minute was reached.

8.13.2.10 `const int ErrorCode.InternalServerError = -1`

(-1) Something went wrong in the server. Try to reproduce and contact Exit Games.

8.13.2.11 `const int ErrorCode.InvalidAuthentication = 0x7FFF`

(32767) Authentication failed. Possible cause: AppId is unknown to [Photon](#) (in cloud service).

8.13.2.12 `const int ErrorCode.InvalidEncryptionParameters = 32741`

(32741) Server will react with this error if invalid encryption parameters provided by token

8.13.2.13 `const int ErrorCode.InvalidOperation = -2`

(-2) The operation you called could not be executed on the server.

Make sure you are connected to the server you expect.

This code is used in several cases: The arguments/parameters of the operation might be out of range, missing entirely or conflicting. The operation you called is not implemented on the server (application). Server-side plugins affect the available operations.

8.13.2.14 `const int ErrorCode.InvalidOperationCode = -2`

(-2) The operation you called is not implemented on the server (application) you connect to. Make sure you run the fitting applications.

8.13.2.15 `const int ErrorCode.InvalidRegion = 0x7FFF - 11`

(32756) Authorization on the [Photon](#) Cloud failed because the app's subscription does not allow to use a particular region's server.

Some subscription plans for the [Photon](#) Cloud are region-bound. Servers of other regions can't be used then. Check your master server address and compare it with your [Photon](#) Cloud Dashboard's info. <https://www.photonengine.com/dashboard>

OpAuthorize is part of connection workflow but only on the [Photon](#) Cloud, this error can happen. Self-hosted [Photon](#) servers with a CCU limited license won't let a client connect at all.

8.13.2.16 const int ErrorCode.JoinFailedFoundActiveJoiner = 32746

(32746) for join requests. Indicates the list of ActiveActors already contains an actor with the requested ActorNr or UserId.

8.13.2.17 const int ErrorCode.JoinFailedFoundExcludedUserId = 32747

(32747) for join requests. Note: for future use - Indicates the requested UserId was found in the ExcludedList.

8.13.2.18 const int ErrorCode.JoinFailedFoundInactiveJoiner = 32749

(32749) for join requests. Indicates the list of InactiveActors already contains an actor with the requested ActorNr or UserId.

8.13.2.19 const int ErrorCode.JoinFailedPeerAlreadyJoined = 32750

(32750) for join requests. Indicates the current peer already called join and is joined to the room.

8.13.2.20 const int ErrorCode.JoinFailedWithRejoinerNotFound = 32748

(32748) for join requests. Indicates the list of Actors (active and inactive) did not contain an actor with the requested ActorNr or UserId.

8.13.2.21 const int ErrorCode.MaxCcuReached = 0x7FFF - 10

(32757) Authorization on the [Photon](#) Cloud failed because the concurrent users (CCU) limit of the app's subscription is reached.

Unless you have a plan with "CCU Burst", clients might fail the authentication step during connect. Affected client are unable to call operations. Please note that players who end a game and return to the master server will disconnect and re-connect, which means that they just played and are rejected in the next minute / re-connect. This is a temporary measure. Once the CCU is below the limit, players will be able to connect and play again.

OpAuthorize is part of connection workflow but only on the [Photon](#) Cloud, this error can happen. Self-hosted [Photon](#) servers with a CCU limited license won't let a client connect at all.

8.13.2.22 const int ErrorCode.NoRandomMatchFound = 0x7FFF - 7

(32760) Random matchmaking only succeeds if a room exists that's neither closed nor full. Repeat in a few seconds or create a new room.

8.13.2.23 const int ErrorCode.Ok = 0

(0) is always "OK", anything else an error or specific situation.

8.13.2.24 const int ErrorCode.OperationNotAllowedInCurrentState = -3

(-3) Operation can't be executed yet (e.g. OpJoin can't be called before being authenticated, RaiseEvent can't be used before getting into a room).

Before you call any operations on the Cloud servers, the automated client workflow must complete its authorization. In PUN, wait until State is: JoinedLobby (with AutoJoinLobby = true) or ConnectedToMaster (AutoJoinLobby = false)

8.13.2.25 `const int ErrorCode.PluginMismatch = 0x7FFF - 16`

(32751) CreateRoom/JoinRoom/Join operation fails if expected plugin does not correspond to loaded one.

8.13.2.26 `const int ErrorCode.PluginReportedError = 0x7FFF - 15`

(32752) A server-side plugin (or webhook) failed to execute and reported an error. Check the `OperationResponse.DebugMessage`.

8.13.2.27 `const int ErrorCode.ServerFull = 0x7FFF - 5`

(32762) Not in use currently.

8.13.2.28 `const int ErrorCode.SlotError = 32742`

(32742) Server error during matchmaking with slot reservation. E.g. the reserved slots can not exceed `MaxPlayers`.

8.13.2.29 `const int ErrorCode.UserBlocked = 0x7FFF - 6`

(32761) Not in use currently.

8.14 EventCode Class Reference

Class for constants. These values are for events defined by [Photon](#) Loadbalancing.

Public Attributes

- `const byte GameList = 230`
(230) Initial list of RoomInfos (in lobby on Master)
- `const byte GameListUpdate = 229`
(229) Update of RoomInfos to be merged into "initial" list (in lobby on Master)
- `const byte QueueState = 228`
(228) Currently not used. State of queueing in case of server-full
- `const byte Match = 227`
(227) Currently not used. Event for matchmaking
- `const byte AppStats = 226`
(226) Event with stats about this application (players, rooms, etc)
- `const byte LobbyStats = 224`
(224) This event provides a list of lobbies with their player and game counts.
- `const byte AzureNodeInfo = 210`
(210) Internally used in case of hosting by Azure
- `const byte Join = (byte)255`
(255) Event Join: someone joined the game. The new actorNumber is provided as well as the properties of that actor (if set in OpJoin).
- `const byte Leave = (byte)254`
(254) Event Leave: The player who left the game can be identified by the actorNumber.
- `const byte PropertiesChanged = (byte)253`
(253) When you call OpSetProperties with the broadcast option "on", this event is fired. It contains the properties being set.
- `const byte SetPropertyes = (byte)253`

(253) When you call `OpSetProperties` with the broadcast option "on", this event is fired. It contains the properties being set.

- const byte `ErrorInfo` = 251

(252) When player left game unexpected and the room has a `playerTtl > 0`, this event is fired to let everyone know about the timeout.

- const byte `CacheSliceChanged` = 250

(250) Sent by `Photon` when the event cache slice was changed. Done by `OpRaiseEvent`.

- const byte `AuthEvent` = 223

(223) Sent by `Photon` to update a token before it times out.

8.14.1 Detailed Description

Class for constants. These values are for events defined by `Photon` Loadbalancing.

They start at 255 and go DOWN. Your own in-game events can start at 0. Pun uses these constants internally.

8.14.2 Member Data Documentation

8.14.2.1 const byte EventCode.AppStats = 226

(226) Event with stats about this application (players, rooms, etc)

8.14.2.2 const byte EventCode.AuthEvent = 223

(223) Sent by `Photon` to update a token before it times out.

8.14.2.3 const byte EventCode.AzureNodeInfo = 210

(210) Internally used in case of hosting by Azure

8.14.2.4 const byte EventCode.CacheSliceChanged = 250

(250) Sent by `Photon` when the event cache slice was changed. Done by `OpRaiseEvent`.

8.14.2.5 const byte EventCode.ErrorInfo = 251

(252) When player left game unexpected and the room has a `playerTtl > 0`, this event is fired to let everyone know about the timeout.

Obsolete. Replaced by `Leave`. `public const byte Disconnect = LiteEventCode.Disconnect;`

(251) Sent by `Photon` Cloud when a plugin-call or webhook-call failed. Usually, the execution on the server continues, despite the issue. Contains: `ParameterCode.Info`.

See also

<https://doc.photonengine.com/en/realtime/current/reference/webhooks::options>

8.14.2.6 const byte EventCode.GameList = 230

(230) Initial list of `RoomInfos` (in lobby on Master)

8.14.2.7 const byte EventCode.GameListUpdate = 229

(229) Update of RoomInfos to be merged into "initial" list (in lobby on Master)

8.14.2.8 const byte EventCode.Join = (byte)255

(255) Event Join: someone joined the game. The new actorNumber is provided as well as the properties of that actor (if set in OpJoin).

8.14.2.9 const byte EventCode.Leave = (byte)254

(254) Event Leave: The player who left the game can be identified by the actorNumber.

8.14.2.10 const byte EventCode.LobbyStats = 224

(224) This event provides a list of lobbies with their player and game counts.

8.14.2.11 const byte EventCode.Match = 227

(227) Currently not used. Event for matchmaking

8.14.2.12 const byte EventCode.PropertiesChanged = (byte)253

(253) When you call OpSetProperties with the broadcast option "on", this event is fired. It contains the properties being set.

8.14.2.13 const byte EventCode.QueueState = 228

(228) Currently not used. State of queueing in case of server-full

8.14.2.14 const byte EventCode.SetProperties = (byte)253

(253) When you call OpSetProperties with the broadcast option "on", this event is fired. It contains the properties being set.

8.15 Extensions Class Reference

This static class defines some useful extension methods for several existing classes (e.g. Vector3, float and others).

Static Public Member Functions

- static ParameterInfo[] [GetCachedParemeters](#) (this MethodInfo mo)
- static PhotonView[] [GetPhotonViewsInChildren](#) (this UnityEngine.GameObject go)
- static PhotonView [GetPhotonView](#) (this UnityEngine.GameObject go)
- static bool [AlmostEquals](#) (this Vector3 target, Vector3 second, float sqrMagnitudePrecision)
compares the squared magnitude of target - second to given float value
- static bool [AlmostEquals](#) (this Vector2 target, Vector2 second, float sqrMagnitudePrecision)
compares the squared magnitude of target - second to given float value
- static bool [AlmostEquals](#) (this Quaternion target, Quaternion second, float maxAngle)

- compares the angle between target and second to given float value*
- static bool [AlmostEquals](#) (this float target, float second, float floatDiff)
compares two floats and returns true if their difference is less than floatDiff
- static void [Merge](#) (this IDictionary target, IDictionary addHash)
Merges all keys from addHash into the target. Adds new keys and updates the values of existing keys in target.
- static void [MergeStringKeys](#) (this IDictionary target, IDictionary addHash)
Merges keys of type string to target Hashtable.
- static string [ToStringFull](#) (this IDictionary origin)
Helper method for debugging of IDictionary content, including type-information. Using this is not performant.
- static string [ToStringFull](#) (this object[] data)
Helper method for debugging of object[] content. Using this is not performant.
- static [Hashtable StripToStringKeys](#) (this IDictionary original)
This method copies all string-typed keys of the original into a new Hashtable.
- static void [StripKeysWithNullValues](#) (this IDictionary original)
This removes all key-value pairs that have a null-reference as value. [Photon](#) properties are removed by setting their value to null. Changes the original passed IDictionary!
- static bool [Contains](#) (this int[] target, int nr)
Checks if a particular integer value is in an int-array.

Static Public Attributes

- static Dictionary< MethodInfo, ParameterInfo[]> [ParametersOfMethods](#) = new Dictionary<MethodInfo, ParameterInfo[]>()

8.15.1 Detailed Description

This static class defines some useful extension methods for several existing classes (e.g. Vector3, float and others).

8.15.2 Member Function Documentation

8.15.2.1 static bool Extensions.AlmostEquals (this Vector3 target, Vector3 second, float sqrMagnitudePrecision)
[static]

compares the squared magnitude of target - second to given float value

8.15.2.2 static bool Extensions.AlmostEquals (this Vector2 target, Vector2 second, float sqrMagnitudePrecision)
[static]

compares the squared magnitude of target - second to given float value

8.15.2.3 static bool Extensions.AlmostEquals (this Quaternion target, Quaternion second, float maxAngle) [static]

compares the angle between target and second to given float value

8.15.2.4 static bool Extensions.AlmostEquals (this float target, float second, float floatDiff) [static]

compares two floats and returns true if their difference is less than floatDiff

8.15.2.5 `static bool Extensions.Contains (this int[] target, int nr)` `[static]`

Checks if a particular integer value is in an int-array.

This might be useful to look up if a particular actorNumber is in the list of players of a room.

Parameters

<i>target</i>	The array of ints to check.
<i>nr</i>	The number to lookup in target.

Returns

True if nr was found in target.

8.15.2.6 `static ParameterInfo [] Extensions.GetCachedParameters (this MethodInfo mo) [static]`

8.15.2.7 `static PhotonView Extensions.GetPhotonView (this UnityEngine.GameObject go) [static]`

8.15.2.8 `static PhotonView [] Extensions.GetPhotonViewsInChildren (this UnityEngine.GameObject go) [static]`

8.15.2.9 `static void Extensions.Merge (this IDictionary target, IDictionary addHash) [static]`

Merges all keys from addHash into the target. Adds new keys and updates the values of existing keys in target.

Parameters

<i>target</i>	The IDictionary to update.
<i>addHash</i>	The IDictionary containing data to merge into target.

8.15.2.10 `static void Extensions.MergeStringKeys (this IDictionary target, IDictionary addHash) [static]`

Merges keys of type string to target Hashtable.

Does not remove keys from target (so non-string keys CAN be in target if they were before).

Parameters

<i>target</i>	The target IDictionary passed in plus all string-typed keys from the addHash.
<i>addHash</i>	A IDictionary that should be merged partly into target to update it.

8.15.2.11 `static void Extensions.StripKeysWithNullValues (this IDictionary original) [static]`

This removes all key-value pairs that have a null-reference as value. [Photon](#) properties are removed by setting their value to null. Changes the original passed IDictionary!

Parameters

<i>original</i>	The IDictionary to strip of keys with null-values.
-----------------	--

8.15.2.12 `static Hashtable Extensions.StripToStringKeys (this IDictionary original) [static]`

This method copies all string-typed keys of the original into a new Hashtable.

Does not recurse (!) into hashes that might be values in the root-hash. This does not modify the original.

Parameters

<i>original</i>	The original IDictionary to get string-typed keys from.
-----------------	---

Returns

New Hashtable containing only string-typed keys of the original.

8.15.2.13 static string Extensions.ToStringFull (this IDictionary *origin*) [static]

Helper method for debugging of IDictionary content, including type-information. Using this is not performant.
Should only be used for debugging as necessary.

Parameters

<i>origin</i>	Some Dictionary or Hashtable.
---------------	-------------------------------

Returns

String of the content of the IDictionary.

8.15.2.14 static string Extensions.ToStringFull (this object[] *data*) [static]

Helper method for debugging of object[] content. Using this is not performant.
Should only be used for debugging as necessary.

Parameters

<i>data</i>	Any object[].
-------------	---------------

Returns

A comma-separated string containing each value's ToString().

8.15.3 Member Data Documentation

8.15.3.1 Dictionary<MethodInfo, ParameterInfo[]> Extensions.ParametersOfMethods = new Dictionary<MethodInfo, ParameterInfo[]>() [static]

8.16 FriendInfo Class Reference

Used to store info about a friend's online state and in which room he/she is.

Public Member Functions

- override string [ToString](#) ()

Properties

- string [Name](#) [get, set]
- bool [IsOnline](#) [get, set]
- string [Room](#) [get, set]
- bool [IsInRoom](#) [get]

8.16.1 Detailed Description

Used to store info about a friend's online state and in which room he/she is.

8.16.2 Member Function Documentation

8.16.2.1 `override string FriendInfo.ToString ()`

8.16.3 Property Documentation

8.16.3.1 `bool FriendInfo.IsInRoom` `[get]`

8.16.3.2 `bool FriendInfo.IsOnline` `[get]`, `[set]`

8.16.3.3 `string FriendInfo.Name` `[get]`, `[set]`

8.16.3.4 `string FriendInfo.Room` `[get]`, `[set]`

8.17 GameObjectExtensions Class Reference

Small number of extension methods that make it easier for PUN to work cross-Unity-versions.

Static Public Member Functions

- static bool [GetActive](#) (this GameObject target)
Unity-version-independent replacement for active GO property.

8.17.1 Detailed Description

Small number of extension methods that make it easier for PUN to work cross-Unity-versions.

8.17.2 Member Function Documentation

8.17.2.1 `static bool GameObjectExtensions.GetActive (this GameObject target)` `[static]`

Unity-version-independent replacement for active GO property.

Returns

Unity 3.5: active. Any newer Unity: activeInHierarchy.

8.18 GamePropertyKey Class Reference

Class for constants. These (byte) values are for "well known" room/game properties used in [Photon](#) Loadbalancing.

Public Attributes

- const byte [MaxPlayers](#) = 255
(255) Max number of players that "fit" into this room. 0 is for "unlimited".
- const byte [IsVisible](#) = 254
(254) Makes this room listed or not in the lobby on master.
- const byte [IsOpen](#) = 253
(253) Allows more players to join a room (or not).
- const byte [PlayerCount](#) = 252
(252) Current count of players in the room. Used only in the lobby on master.

- const byte [Removed](#) = 251
(251) True if the room is to be removed from room listing (used in update to room list in lobby on master)
- const byte [PropsListedInLobby](#) = 250
(250) A list of the room properties to pass to the [RoomInfo](#) list in a lobby. This is used in `CreateRoom`, which defines this list once per room.
- const byte [CleanupCacheOnLeave](#) = 249
(249) Equivalent of Operation Join parameter `CleanupCacheOnLeave`.
- const byte [MasterClientId](#) = (byte)248
(248) Code for `MasterClientId`, which is synced by server. When sent as op-parameter this is (byte)203. As room property this is (byte)248.
- const byte [ExpectedUsers](#) = (byte)247
(247) Code for `ExpectedUsers` in a room. Matchmaking keeps a slot open for the players with these userIDs.

8.18.1 Detailed Description

Class for constants. These (byte) values are for "well known" room/game properties used in [Photon](#) Loadbalancing. Pun uses these constants internally. "Custom properties" have to use a string-type as key. They can be assigned at will.

8.18.2 Member Data Documentation

8.18.2.1 const byte `GamePropertyKey.CleanupCacheOnLeave` = 249

(249) Equivalent of Operation Join parameter `CleanupCacheOnLeave`.

8.18.2.2 const byte `GamePropertyKey.ExpectedUsers` = (byte)247

(247) Code for `ExpectedUsers` in a room. Matchmaking keeps a slot open for the players with these userIDs.

8.18.2.3 const byte `GamePropertyKey.IsOpen` = 253

(253) Allows more players to join a room (or not).

8.18.2.4 const byte `GamePropertyKey.IsVisible` = 254

(254) Makes this room listed or not in the lobby on master.

8.18.2.5 const byte `GamePropertyKey.MasterClientId` = (byte)248

(248) Code for `MasterClientId`, which is synced by server. When sent as op-parameter this is (byte)203. As room property this is (byte)248.

Tightly related to [ParameterCode.MasterClientId](#).

8.18.2.6 const byte `GamePropertyKey.MaxPlayers` = 255

(255) Max number of players that "fit" into this room. 0 is for "unlimited".

8.18.2.7 const byte `GamePropertyKey.PlayerCount` = 252

(252) Current count of players in the room. Used only in the lobby on master.

8.18.2.8 `const byte GamePropertyKey.PropsListedInLobby = 250`

(250) A list of the room properties to pass to the [RoomInfo](#) list in a lobby. This is used in `CreateRoom`, which defines this list once per room.

8.18.2.9 `const byte GamePropertyKey.Removed = 251`

(251) True if the room is to be removed from room listing (used in update to room list in lobby on master)

8.19 ExitGames.Client.GUI.GizmoTypeDrawer Class Reference

Static Public Member Functions

- static void [Draw](#) (Vector3 center, [GizmoType](#) type, Color color, float size)

8.19.1 Member Function Documentation

8.19.1.1 `static void ExitGames.Client.GUI.GizmoTypeDrawer.Draw (Vector3 center, GizmoType type, Color color, float size)`
[static]

8.20 HelpURL Class Reference

Empty implementation of the upcoming [HelpURL](#) of Unity 5.1. This one is only for compatibility of attributes.

Inherits [Attribute](#).

Public Member Functions

- [HelpURL](#) (string url)

8.20.1 Detailed Description

Empty implementation of the upcoming [HelpURL](#) of Unity 5.1. This one is only for compatibility of attributes.

<http://feedback.unity3d.com/suggestions/override-component-documentation-slash-help-link>

8.20.2 Constructor & Destructor Documentation

8.20.2.1 `HelpURL.HelpURL (string url)`

8.21 ExitGames.Client.Photon.Chat.IChatClientListener Interface Reference

Callback interface for [Chat](#) client side. Contains callback methods to notify your app about updates. Must be provided to new [ChatClient](#) in constructor

Public Member Functions

- void [DebugReturn](#) (DebugLevel level, string message)
All debug output of the library will be reported through this method. Print it or put it in a buffer to use it on-screen.
- void [OnDisconnected](#) ()

- Disconnection happened.*
- void **OnConnected** ()
 - Client is connected now.*
- void **OnChatStateChange** (**ChatState** state)
 - The ChatClient's state changed. Usually, OnConnected and OnDisconnected are the callbacks to react to.*
- void **OnGetMessages** (string channelName, string[] senders, object[] messages)
 - Notifies app that client got new messages from server Number of senders is equal to number of messages in 'messages'. Sender with number '0' corresponds to message with number '0', sender with number '1' corresponds to message with number '1' and so on*
- void **OnPrivateMessage** (string sender, object message, string channelName)
 - Notifies client about private message*
- void **OnSubscribed** (string[] channels, bool[] results)
 - Result of Subscribe operation. Returns subscription result for every requested channel name.*
- void **OnUnsubscribed** (string[] channels)
 - Result of Unsubscribe operation. Returns for channel name if the channel is now unsubscribed.*
- void **OnStatusUpdate** (string user, int status, bool gotMessage, object message)
 - New status of another user (you get updates for users set in your friends list).*

8.21.1 Detailed Description

Callback interface for **Chat** client side. Contains callback methods to notify your app about updates. Must be provided to new **ChatClient** in constructor

8.21.2 Member Function Documentation

8.21.2.1 void ExitGames.Client.Photon.Chat.IChatClientListener.DebugReturn (DebugLevel level, string message)

All debug output of the library will be reported through this method. Print it or put it in a buffer to use it on-screen.

Parameters

<i>level</i>	DebugLevel (severity) of the message.
<i>message</i>	Debug text. Print to System.Console or screen.

8.21.2.2 void ExitGames.Client.Photon.Chat.IChatClientListener.OnChatStateChange (ChatState state)

The **ChatClient**'s state changed. Usually, OnConnected and OnDisconnected are the callbacks to react to.

Parameters

<i>state</i>	The new state.
--------------	----------------

8.21.2.3 void ExitGames.Client.Photon.Chat.IChatClientListener.OnConnected ()

Client is connected now.

Clients have to be connected before they can send their state, subscribe to channels and send any messages.

8.21.2.4 void ExitGames.Client.Photon.Chat.IChatClientListener.OnDisconnected ()

Disconnection happened.

8.21.2.5 void ExitGames.Client.Photon.Chat.IChatClientListener.OnGetMessages (string *channelName*, string[] *senders*, object[] *messages*)

Notifies app that client got new messages from server Number of senders is equal to number of messages in 'messages'. Sender with number '0' corresponds to message with number '0', sender with number '1' corresponds to message with number '1' and so on

Parameters

<i>channelName</i>	channel from where messages came
<i>senders</i>	list of users who sent messages
<i>messages</i>	list of messages it self

8.21.2.6 void ExitGames.Client.Photon.Chat.IChatClientListener.OnPrivateMessage (string *sender*, object *message*, string *channelName*)

Notifies client about private message

Parameters

<i>sender</i>	user who sent this message
<i>message</i>	message it self
<i>channelName</i>	channelName for private messages (messages you sent yourself get added to a channel per target username)

8.21.2.7 void ExitGames.Client.Photon.Chat.IChatClientListener.OnStatusUpdate (string *user*, int *status*, bool *gotMessage*, object *message*)

New status of another user (you get updates for users set in your friends list).

Parameters

<i>user</i>	Name of the user.
<i>status</i>	New status of that user.
<i>gotMessage</i>	True if the status contains a message you should cache locally. False: This status update does not include a message (keep any you have).
<i>message</i>	Message that user set.

8.21.2.8 void ExitGames.Client.Photon.Chat.IChatClientListener.OnSubscribed (string[] *channels*, bool[] *results*)

Result of Subscribe operation. Returns subscription result for every requested channel name.

If multiple channels sent in Subscribe operation, OnSubscribed may be called several times, each call with part of sent array or with single channel in "channels" parameter. Calls order and order of channels in "channels" parameter may differ from order of channels in "channels" parameter of Subscribe operation.

Parameters

<i>channels</i>	Array of channel names.
<i>results</i>	Per channel result if subscribed.

8.21.2.9 void ExitGames.Client.Photon.Chat.IChatClientListener.OnUnsubscribed (string[] *channels*)

Result of Unsubscribe operation. Returns for channel name if the channel is now unsubscribed.

If multiple channels sent in Unsubscribe operation, OnUnsubscribed may be called several times, each call with part of sent array or with single channel in "channels" parameter. Calls order and order of channels in "channels"

parameter may differ from order of channels in "channels" parameter of Unsubscribe operation.

Parameters

<i>channels</i>	Array of channel names that are no longer subscribed.
-----------------	---

8.22 IPunCallbacks Interface Reference

This interface is used as definition of all callback methods of PUN, except `OnPhotonSerializeView`. Preferably, implement them individually.

Inherited by [Photon.PunBehaviour](#).

Public Member Functions

- void [OnConnectedToPhoton](#) ()
Called when the initial connection got established but before you can use the server. [OnJoinedLobby\(\)](#) or [OnConnectedToMaster\(\)](#) are called when PUN is ready.
- void [OnLeftRoom](#) ()
Called when the local user/client left a room.
- void [OnMasterClientSwitched](#) ([PhotonPlayer](#) newMasterClient)
Called after switching to a new MasterClient when the current one leaves.
- void [OnPhotonCreateRoomFailed](#) (object[] codeAndMsg)
Called when a [CreateRoom\(\)](#) call failed. The parameter provides [ErrorCode](#) and message (as array).
- void [OnPhotonJoinRoomFailed](#) (object[] codeAndMsg)
Called when a [JoinRoom\(\)](#) call failed. The parameter provides [ErrorCode](#) and message (as array).
- void [OnCreatedRoom](#) ()
Called when this client created a room and entered it. [OnJoinedRoom\(\)](#) will be called as well.
- void [OnJoinedLobby](#) ()
Called on entering a lobby on the Master Server. The actual room-list updates will call [OnReceivedRoomListUpdate\(\)](#).
- void [OnLeftLobby](#) ()
Called after leaving a lobby.
- void [OnFailedToConnectToPhoton](#) ([DisconnectCause](#) cause)
Called if a connect call to the [Photon](#) server failed before the connection was established, followed by a call to [OnDisconnectedFromPhoton\(\)](#).
- void [OnConnectionFail](#) ([DisconnectCause](#) cause)
Called when something causes the connection to fail (after it was established), followed by a call to [OnDisconnectedFromPhoton\(\)](#).
- void [OnDisconnectedFromPhoton](#) ()
Called after disconnecting from the [Photon](#) server.
- void [OnPhotonInstantiate](#) ([PhotonMessageInfo](#) info)
Called on all scripts on a [GameObject](#) (and children) that have been instantiated using [PhotonNetwork.Instantiate](#).
- void [OnReceivedRoomListUpdate](#) ()
Called for any update of the room-listing while in a lobby ([PhotonNetwork.insideLobby](#)) on the Master Server.
- void [OnJoinedRoom](#) ()
Called when entering a room (by creating or joining it). Called on all clients (including the Master Client).
- void [OnPhotonPlayerConnected](#) ([PhotonPlayer](#) newPlayer)
Called when a remote player entered the room. This [PhotonPlayer](#) is already added to the playerlist at this time.
- void [OnPhotonPlayerDisconnected](#) ([PhotonPlayer](#) otherPlayer)
Called when a remote player left the room. This [PhotonPlayer](#) is already removed from the playerlist at this time.
- void [OnPhotonRandomJoinFailed](#) (object[] codeAndMsg)
Called when a [JoinRandom\(\)](#) call failed. The parameter provides [ErrorCode](#) and message.
- void [OnConnectedToMaster](#) ()

Called after the connection to the master is established and authenticated but only when [PhotonNetwork.autoJoinLobby](#) is false.

- void [OnPhotonMaxCccuReached](#) ()
Because the concurrent user limit was (temporarily) reached, this client is rejected by the server and disconnecting.
- void [OnPhotonCustomRoomPropertiesChanged](#) (Hashtable propertiesThatChanged)
Called when a room's custom properties changed. The propertiesThatChanged contains all that was set via [Room.SetCustomProperties](#).
- void [OnPhotonPlayerPropertiesChanged](#) (object[] playerAndUpdatedProps)
Called when custom player-properties are changed. Player and the changed properties are passed as object[].
- void [OnUpdatedFriendList](#) ()
Called when the server sent the response to a FindFriends request and updated [PhotonNetwork.Friends](#).
- void [OnCustomAuthenticationFailed](#) (string debugMessage)
Called when the custom authentication failed. Followed by disconnect!
- void [OnCustomAuthenticationResponse](#) (Dictionary< string, object > data)
Called when your Custom Authentication service responds with additional data.
- void [OnWebRpcResponse](#) (OperationResponse response)
Called by PUN when the response to a WebRPC is available. See [PhotonNetwork.WebRPC](#).
- void [OnOwnershipRequest](#) (object[] viewAndPlayer)
Called when another player requests ownership of a [PhotonView](#) from you (the current owner).
- void [OnLobbyStatisticsUpdate](#) ()
Called when the Master Server sent an update for the Lobby Statistics, updating [PhotonNetwork.LobbyStatistics](#).
- void [OnPhotonPlayerActivityChanged](#) (PhotonPlayer otherPlayer)
Called when a remote [Photon](#) Player activity changed. This will be called ONLY if PlayerTtl is greater than 0.
- void [OnOwnershipTransferred](#) (object[] viewAndPlayers)
Called when ownership of a [PhotonView](#) is transferred to another player.

8.22.1 Detailed Description

This interface is used as definition of all callback methods of PUN, except [OnPhotonSerializeView](#). Preferably, implement them individually.

This interface is available for completeness, more than for actually implementing it in a game. You can implement each method individually in any MonoBehaviour, without implementing [IPunCallbacks](#).

PUN calls all callbacks by name. Don't use implement callbacks with fully qualified name. Example: [IPunCallbacks.OnConnectedToPhoton](#) won't get called by Unity's [SendMessage\(\)](#).

PUN will call these methods on any script that implements them, analog to Unity's events and callbacks. The situation that triggers the call is described per method.

[OnPhotonSerializeView](#) is NOT called like these callbacks! It's usage frequency is much higher and it is implemented in: [IPunObservable](#).

8.22.2 Member Function Documentation

8.22.2.1 void IPunCallbacks.OnConnectedToMaster ()

Called after the connection to the master is established and authenticated but only when [PhotonNetwork.autoJoinLobby](#) is false.

If you set [PhotonNetwork.autoJoinLobby](#) to true, [OnJoinedLobby\(\)](#) will be called instead of this.

You can join rooms and create them even without being in a lobby. The default lobby is used in that case. The list of available rooms won't become available unless you join a lobby via [PhotonNetwork.joinLobby](#).

Implemented in [Photon.PunBehaviour](#).

8.22.2.2 void IPunCallbacks.OnConnectedToPhoton ()

Called when the initial connection got established but before you can use the server. [OnJoinedLobby\(\)](#) or [OnConnectedToMaster\(\)](#) are called when PUN is ready.

This callback is only useful to detect if the server can be reached at all (technically). Most often, it's enough to implement [OnFailedToConnectToPhoton\(\)](#) and [OnDisconnectedFromPhoton\(\)](#).

[OnJoinedLobby\(\)](#) or [OnConnectedToMaster\(\)](#) are called when PUN is ready.

When this is called, the low level connection is established and PUN will send your AppId, the user, etc in the background. This is not called for transitions from the masterserver to game servers.

Implemented in [Photon.PunBehaviour](#).

8.22.2.3 void IPunCallbacks.OnConnectionFail (DisconnectCause cause)

Called when something causes the connection to fail (after it was established), followed by a call to [OnDisconnectedFromPhoton\(\)](#).

If the server could not be reached in the first place, [OnFailedToConnectToPhoton](#) is called instead. The reason for the error is provided as [DisconnectCause](#).

Implemented in [Photon.PunBehaviour](#).

8.22.2.4 void IPunCallbacks.OnCreatedRoom ()

Called when this client created a room and entered it. [OnJoinedRoom\(\)](#) will be called as well.

This callback is only called on the client which created a room (see [PhotonNetwork.CreateRoom](#)).

As any client might close (or drop connection) anytime, there is a chance that the creator of a room does not execute [OnCreatedRoom](#).

If you need specific room properties or a "start signal", it is safer to implement [OnMasterClientSwitched\(\)](#) and to make the new [MasterClient](#) check the room's state.

Implemented in [Photon.PunBehaviour](#).

8.22.2.5 void IPunCallbacks.OnCustomAuthenticationFailed (string debugMessage)

Called when the custom authentication failed. Followed by disconnect!

Custom Authentication can fail due to user-input, bad tokens/secrets. If authentication is successful, this method is not called. Implement [OnJoinedLobby\(\)](#) or [OnConnectedToMaster\(\)](#) (as usual).

During development of a game, it might also fail due to wrong configuration on the server side. In those cases, logging the [debugMessage](#) is very important.

Unless you setup a custom authentication service for your app (in the [Dashboard](#)), this won't be called!

Parameters

<i>debugMessage</i>	Contains a debug message why authentication failed. This has to be fixed during development time.
---------------------	---

Implemented in [Photon.PunBehaviour](#).

8.22.2.6 void IPunCallbacks.OnCustomAuthenticationResponse (Dictionary< string, object > data)

Called when your Custom Authentication service responds with additional data.

Custom Authentication services can include some custom data in their response. When present, that data is made available in this callback as [Dictionary](#). While the keys of your data have to be strings, the values can be either string

or a number (in Json). You need to make extra sure, that the value type is the one you expect. Numbers become (currently) int64.

Example: `void OnCustomAuthenticationResponse(Dictionary<string, object> data) { ... }`

<https://doc.photonengine.com/en/realtime/current/reference/custom-authentication>

Implemented in [Photon.PunBehaviour](#).

8.22.2.7 void IPunCallbacks.OnDisconnectedFromPhoton ()

Called after disconnecting from the [Photon](#) server.

In some cases, other callbacks are called before `OnDisconnectedFromPhoton` is called. Examples: [OnConnectionFail\(\)](#) and [OnFailedToConnectToPhoton\(\)](#).

Implemented in [Photon.PunBehaviour](#).

8.22.2.8 void IPunCallbacks.OnFailedToConnectToPhoton (DisconnectCause cause)

Called if a connect call to the [Photon](#) server failed before the connection was established, followed by a call to [OnDisconnectedFromPhoton\(\)](#).

This is called when no connection could be established at all. It differs from `OnConnectionFail`, which is called when an existing connection fails.

Implemented in [Photon.PunBehaviour](#).

8.22.2.9 void IPunCallbacks.OnJoinedLobby ()

Called on entering a lobby on the Master Server. The actual room-list updates will call [OnReceivedRoomListUpdate\(\)](#).

Note: When [PhotonNetwork.autoJoinLobby](#) is false, [OnConnectedToMaster\(\)](#) will be called and the room list won't become available.

While in the lobby, the roomlist is automatically updated in fixed intervals (which you can't modify). The room list gets available when [OnReceivedRoomListUpdate\(\)](#) gets called after [OnJoinedLobby\(\)](#).

Implemented in [Photon.PunBehaviour](#).

8.22.2.10 void IPunCallbacks.OnJoinedRoom ()

Called when entering a room (by creating or joining it). Called on all clients (including the Master Client).

This method is commonly used to instantiate player characters. If a match has to be started "actively", you can call an [PunRPC](#) triggered by a user's button-press or a timer.

When this is called, you can usually already access the existing players in the room via [PhotonNetwork.playerList](#). Also, all custom properties should be already available as [Room.customProperties](#). Check [Room.playerCount](#) to find out if enough players are in the room to start playing.

Implemented in [Photon.PunBehaviour](#).

8.22.2.11 void IPunCallbacks.OnLeftLobby ()

Called after leaving a lobby.

When you leave a lobby, [CreateRoom](#) and [JoinRandomRoom](#) automatically refer to the default lobby.

Implemented in [Photon.PunBehaviour](#).

8.22.2.12 void IPunCallbacks.OnLeftRoom ()

Called when the local user/client left a room.

When leaving a room, PUN brings you back to the Master Server. Before you can use lobbies and join or create rooms, [OnJoinedLobby\(\)](#) or [OnConnectedToMaster\(\)](#) will get called again.

Implemented in [Photon.PunBehaviour](#).

8.22.2.13 void IPunCallbacks.OnLobbyStatisticsUpdate ()

Called when the Master Server sent an update for the Lobby Statistics, updating [PhotonNetwork.LobbyStatistics](#).

This callback has two preconditions: `EnableLobbyStatistics` must be set to true, before this client connects. And the client has to be connected to the Master Server, which is providing the info about lobbies.

Implemented in [Photon.PunBehaviour](#).

8.22.2.14 void IPunCallbacks.OnMasterClientSwitched (PhotonPlayer newMasterClient)

Called after switching to a new MasterClient when the current one leaves.

This is not called when this client enters a room. The former MasterClient is still in the player list when this method get called.

Implemented in [Photon.PunBehaviour](#).

8.22.2.15 void IPunCallbacks.OnOwnershipRequest (object[] viewAndPlayer)

Called when another player requests ownership of a [PhotonView](#) from you (the current owner).

The parameter `viewAndPlayer` contains:

[PhotonView](#) `view` = `viewAndPlayer[0]` as [PhotonView](#);

[PhotonPlayer](#) `requestingPlayer` = `viewAndPlayer[1]` as [PhotonPlayer](#);

Parameters

<i>viewAndPlayer</i>	The PhotonView is <code>viewAndPlayer[0]</code> and the requesting player is <code>viewAndPlayer[1]</code> .
----------------------	--

Implemented in [Photon.PunBehaviour](#).

8.22.2.16 void IPunCallbacks.OnOwnershipTransferred (object[] viewAndPlayers)

Called when ownership of a [PhotonView](#) is transferred to another player.

The parameter `viewAndPlayers` contains:

[PhotonView](#) `view` = `viewAndPlayers[0]` as [PhotonView](#);

[PhotonPlayer](#) `newOwner` = `viewAndPlayers[1]` as [PhotonPlayer](#);

[PhotonPlayer](#) `oldOwner` = `viewAndPlayers[2]` as [PhotonPlayer](#);

`void OnOwnershipTransferred(object[] viewAndPlayers) {} //`

Implemented in [Photon.PunBehaviour](#).

8.22.2.17 void IPunCallbacks.OnPhotonCreateRoomFailed (object[] codeAndMsg)

Called when a [CreateRoom\(\)](#) call failed. The parameter provides [ErrorCode](#) and message (as array).

Most likely because the room name is already in use (some other client was faster than you). PUN logs some info if the [PhotonNetwork.logLevel](#) is \geq PhotonLogLevel.Informational.

Parameters

<i>codeAndMsg</i>	codeAndMsg[0] is short ErrorCode and codeAndMsg[1] is a string debug msg.
-------------------	---

Implemented in [Photon.PunBehaviour](#).

8.22.2.18 void IPunCallbacks.OnPhotonCustomRoomPropertiesChanged (Hashtable *propertiesThatChanged*)

Called when a room's custom properties changed. The *propertiesThatChanged* contains all that was set via [Room.SetCustomProperties](#).

Since v1.25 this method has one parameter: Hashtable *propertiesThatChanged*.

Changing properties must be done by [Room.SetCustomProperties](#), which causes this callback locally, too.

Parameters

<i>propertiesThat↔ Changed</i>	
------------------------------------	--

Implemented in [Photon.PunBehaviour](#).

8.22.2.19 void IPunCallbacks.OnPhotonInstantiate (PhotonMessageInfo *info*)

Called on all scripts on a GameObject (and children) that have been Instantiated using [PhotonNetwork.Instantiate](#). [PhotonMessageInfo](#) parameter provides info about who created the object and when (based off Photon↔Networking.time).

Implemented in [Photon.PunBehaviour](#).

8.22.2.20 void IPunCallbacks.OnPhotonJoinRoomFailed (object[] *codeAndMsg*)

Called when a [JoinRoom\(\)](#) call failed. The parameter provides [ErrorCode](#) and message (as array).

Most likely error is that the room does not exist or the room is full (some other client was faster than you). PUN logs some info if the [PhotonNetwork.logLevel](#) is \geq PhotonLogLevel.Informational.

Parameters

<i>codeAndMsg</i>	codeAndMsg[0] is short ErrorCode and codeAndMsg[1] is string debug msg.
-------------------	---

Implemented in [Photon.PunBehaviour](#).

8.22.2.21 void IPunCallbacks.OnPhotonMaxCcuReached ()

Because the concurrent user limit was (temporarily) reached, this client is rejected by the server and disconnecting.

When this happens, the user might try again later. You can't create or join rooms in [OnPhotonMaxCcuReached\(\)](#), cause the client will be disconnecting. You can raise the CCU limits with a new license (when you host yourself) or extended subscription (when using the [Photon](#) Cloud). The [Photon](#) Cloud will mail you when the CCU limit was reached. This is also visible in the Dashboard (webpage).

Implemented in [Photon.PunBehaviour](#).

8.22.2.22 void IPunCallbacks.OnPhotonPlayerActivityChanged (PhotonPlayer *otherPlayer*)

Called when a remote [Photon](#) Player activity changed. This will be called ONLY if PlayerTtl is greater than 0.

Use [PhotonPlayer.IsInactive](#) to check a player's current activity state.

Example: void [OnPhotonPlayerActivityChanged](#)([PhotonPlayer](#) *otherPlayer*) {...}

This callback has precondition: `PlayerTtl` must be greater than 0.

Implemented in [Photon.PunBehaviour](#).

8.22.2.23 void IPunCallbacks.OnPhotonPlayerConnected ([PhotonPlayer](#) *newPlayer*)

Called when a remote player entered the room. This [PhotonPlayer](#) is already added to the playerlist at this time.

If your game starts with a certain number of players, this callback can be useful to check the [Room.playerCount](#) and find out if you can start.

Implemented in [Photon.PunBehaviour](#).

8.22.2.24 void IPunCallbacks.OnPhotonPlayerDisconnected ([PhotonPlayer](#) *otherPlayer*)

Called when a remote player left the room. This [PhotonPlayer](#) is already removed from the playerlist at this time.

When your client calls `PhotonNetwork.leaveRoom`, PUN will call this method on the remaining clients. When a remote client drops connection or gets closed, this callback gets executed. after a timeout of several seconds.

Implemented in [Photon.PunBehaviour](#).

8.22.2.25 void IPunCallbacks.OnPhotonPlayerPropertiesChanged (object[] *playerAndUpdatedProps*)

Called when custom player-properties are changed. Player and the changed properties are passed as `object[]`.

Since v1.25 this method has one parameter: `object[] playerAndUpdatedProps`, which contains two entries.

[0] is the affected [PhotonPlayer](#).

[1] is the Hashtable of properties that changed.

We are using a `object[]` due to limitations of Unity's `GameObject.SendMessage` (which has only one optional parameter).

Changing properties must be done by [PhotonPlayer.SetCustomProperties](#), which causes this callback locally, too.

Example:

```
void OnPhotonPlayerPropertiesChanged(object[] playerAndUpdatedProps) {
    PhotonPlayer player = playerAndUpdatedProps[0] as PhotonPlayer;
    Hashtable props = playerAndUpdatedProps[1] as Hashtable;
    //...
}
```

Parameters

<i>playerAndUpdatedProps</i>	Contains PhotonPlayer and the properties that changed See remarks.
------------------------------	--

Implemented in [Photon.PunBehaviour](#).

8.22.2.26 void IPunCallbacks.OnPhotonRandomJoinFailed (object[] *codeAndMsg*)

Called when a `JoinRandom()` call failed. The parameter provides [ErrorCode](#) and message.

Most likely all rooms are full or no rooms are available.

When using multiple lobbies (via `JoinLobby` or [TypedLobby](#)), another lobby might have more/fitting rooms.

PUN logs some info if the [PhotonNetwork.logLevel](#) is `>= PhotonLogLevel.Informational`.

Parameters

<i>codeAndMsg</i>	codeAndMsg[0] is short ErrorCode . codeAndMsg[1] is string debug msg.
-------------------	---

Implemented in [Photon.PunBehaviour](#).

8.22.2.27 void IPunCallbacks.OnReceivedRoomListUpdate ()

Called for any update of the room-listing while in a lobby ([PhotonNetwork.insideLobby](#)) on the Master Server.

PUN provides the list of rooms by [PhotonNetwork.GetRoomList\(\)](#).

Each item is a [RoomInfo](#) which might include custom properties (provided you defined those as lobby-listed when creating a room).

Not all types of lobbies provide a listing of rooms to the client. Some are silent and specialized for server-side matchmaking.

Implemented in [Photon.PunBehaviour](#).

8.22.2.28 void IPunCallbacks.OnUpdatedFriendList ()

Called when the server sent the response to a FindFriends request and updated [PhotonNetwork.Friends](#).

The friends list is available as [PhotonNetwork.Friends](#), listing name, online state and the room a user is in (if any).

Implemented in [Photon.PunBehaviour](#).

8.22.2.29 void IPunCallbacks.OnWebRpcResponse (OperationResponse *response*)

Called by PUN when the response to a WebRPC is available. See [PhotonNetwork.WebRPC](#).

Important: The response.ReturnCode is 0 if [Photon](#) was able to reach your web-service.

The content of the response is what your web-service sent. You can create a [WebRpcResponse](#) from it.

Example: [WebRpcResponse](#) webResponse = new [WebRpcResponse\(operationResponse\)](#);

Please note: Class OperationResponse is in a namespace which needs to be "used":
using [ExitGames.Client.Photon](#); // includes OperationResponse (and other classes)

The OperationResponse.ReturnCode by [Photon](#) is:

```
0 for "OK"
-3 for "Web-Service not configured" (see Dashboard / WebHooks)
-5 for "Web-Service does now have RPC path/name" (at least for Azure)
```

Implemented in [Photon.PunBehaviour](#).

8.23 IPunObservable Interface Reference

Defines the OnPhotonSerializeView method to make it easy to implement correctly for observable scripts.

Inherited by [PhotonAnimatorView](#), [PhotonRigidbody2DView](#), [PhotonRigidbodyView](#), and [PhotonTransformView](#).

Public Member Functions

- void [OnPhotonSerializeView](#) ([PhotonStream](#) stream, [PhotonMessageInfo](#) info)

Called by PUN several times per second, so that your script can write and read synchronization data for the [Photon<→View](#).

8.23.1 Detailed Description

Defines the OnPhotonSerializeView method to make it easy to implement correctly for observable scripts.

8.24 IPunPrefabPool Interface Reference

Defines all the methods that a Object Pool must implement, so that PUN can use it.

Public Member Functions

- **GameObject** [Instantiate](#) (string prefabId, Vector3 position, Quaternion rotation)
This is called when PUN wants to create a new instance of an entity prefab. Must return valid GameObject with [PhotonView](#).
- void [Destroy](#) (GameObject gameObject)
This is called when PUN wants to destroy the instance of an entity prefab.

8.24.1 Detailed Description

Defines all the methods that a Object Pool must implement, so that PUN can use it.

To use a Object Pool for instantiation, you can set PhotonNetwork.ObjectPool. That is used for all objects, as long as ObjectPool is not null. The pool has to return a valid non-null GameObject when PUN calls Instantiate. Also, the position and rotation must be applied.

Please note that pooled GameObjects don't get the usual Awake and Start calls. OnEnable will be called (by your pool) but the networking values are not updated yet when that happens. OnEnable will have outdated values for [PhotonView](#) (isMine, etc.). You might have to adjust scripts.

PUN will call OnPhotonInstantiate (see [IPunCallbacks](#)). This should be used to setup the re-used object with regards to networking values / ownership.

8.24.2 Member Function Documentation

8.24.2.1 void IPunPrefabPool.Destroy (GameObject *gameObject*)

This is called when PUN wants to destroy the instance of an entity prefab.

A pool needs some way to find out which type of GameObject got returned via [Destroy\(\)](#). It could be a tag or name or anything similar.

Parameters

<i>gameObject</i>	The instance to destroy.
-------------------	--------------------------

8.24.2.2 GameObject IPunPrefabPool.Instantiate (string *prefabId*, Vector3 *position*, Quaternion *rotation*)

This is called when PUN wants to create a new instance of an entity prefab. Must return valid GameObject with [PhotonView](#).

Parameters

<i>prefabId</i>	The id of this prefab.
-----------------	------------------------

<i>position</i>	The position we want the instance instantiated at.
<i>rotation</i>	The rotation we want the instance to take.

Returns

The newly instantiated object, or null if a prefab with *prefabId* was not found.

8.25 Photon.MonoBehaviour Class Reference

This class adds the property `photonView`, while logging a warning when your game still uses the `networkView`.

Inherits `MonoBehaviour`.

Inherited by [Photon.PunBehaviour](#), and [PhotonView](#).

Properties

- [PhotonView](#) `photonView` [get]
A cached reference to a [PhotonView](#) on this `GameObject`.
- new [PhotonView](#) `networkView` [get]
This property is only here to notify developers when they use the outdated value.

8.25.1 Detailed Description

This class adds the property `photonView`, while logging a warning when your game still uses the `networkView`.

8.25.2 Property Documentation

8.25.2.1 new PhotonView Photon.MonoBehaviour.networkView [get]

This property is only here to notify developers when they use the outdated value.

If Unity 5.x logs a compiler warning "Use the new keyword if hiding was intended" or "The new keyword is not required", you may suffer from an Editor issue. Try to modify `networkView` with a `if-def` condition:

```
#if UNITY_EDITOR new #endif public PhotonView networkView
```

8.25.2.2 PhotonView Photon.MonoBehaviour.photonView [get]

A cached reference to a [PhotonView](#) on this `GameObject`.

If you intend to work with a [PhotonView](#) in a script, it's usually easier to write `this.photonView`.

If you intend to remove the [PhotonView](#) component from the `GameObject` but keep this [Photon.MonoBehaviour](#), avoid this reference or modify this code to use `PhotonView.Get(obj)` instead.

8.26 OperationCode Class Reference

Class for constants. Contains operation codes. Pun uses these constants internally.

Public Attributes

- const byte [ExchangeKeysForEncryption](#) = 250
- const byte [Join](#) = 255
(255) Code for OpJoin, to get into a room.
- const byte [AuthenticateOnce](#) = 231
(231) Authenticates this peer and connects to a virtual application
- const byte [Authenticate](#) = 230
(230) Authenticates this peer and connects to a virtual application
- const byte [JoinLobby](#) = 229
(229) Joins lobby (on master)
- const byte [LeaveLobby](#) = 228
(228) Leaves lobby (on master)
- const byte [CreateGame](#) = 227
(227) Creates a game (or fails if name exists)
- const byte [JoinGame](#) = 226
(226) Join game (by name)
- const byte [JoinRandomGame](#) = 225
(225) Joins random game (on master)
- const byte [Leave](#) = (byte)254
(254) Code for OpLeave, to get out of a room.
- const byte [RaiseEvent](#) = (byte)253
(253) Raise event (in a room, for other actors/players)
- const byte [SetProperties](#) = (byte)252
(252) Set Properties (of room or actor/player)
- const byte [GetProperties](#) = (byte)251
(251) Get Properties
- const byte [ChangeGroups](#) = (byte)248
(248) Operation code to change interest groups in Rooms (Lite application and extending ones).
- const byte [FindFriends](#) = 222
(222) Request the rooms and online status for a list of friends (by name, which should be unique).
- const byte [GetLobbyStats](#) = 221
(221) Request statistics about a specific list of lobbies (their user and game count).
- const byte [GetRegions](#) = 220
(220) Get list of regional servers from a NameServer.
- const byte [WebRpc](#) = 219
(219) WebRpc Operation.
- const byte [ServerSettings](#) = 218
(218) Operation to set some server settings. Used with different parameters on various servers.
- const byte [GetGameList](#) = 217
(217) Get the game list matching a supplied sql filter (SqlListLobby only)

8.26.1 Detailed Description

Class for constants. Contains operation codes. Pun uses these constants internally.

8.26.2 Member Data Documentation

8.26.2.1 const byte `OperationCode.Authenticate` = 230

(230) Authenticates this peer and connects to a virtual application

8.26.2.2 `const byte OperationCode.AuthenticateOnce = 231`

(231) Authenticates this peer and connects to a virtual application

8.26.2.3 `const byte OperationCode.ChangeGroups = (byte)248`

(248) Operation code to change interest groups in Rooms (Lite application and extending ones).

8.26.2.4 `const byte OperationCode.CreateGame = 227`

(227) Creates a game (or fails if name exists)

8.26.2.5 `const byte OperationCode.ExchangeKeysForEncryption = 250`

8.26.2.6 `const byte OperationCode.FindFriends = 222`

(222) Request the rooms and online status for a list of friends (by name, which should be unique).

8.26.2.7 `const byte OperationCode.GetGameList = 217`

(217) Get the game list matching a supplied sql filter (SqlListLobby only)

8.26.2.8 `const byte OperationCode.GetLobbyStats = 221`

(221) Request statistics about a specific list of lobbies (their user and game count).

8.26.2.9 `const byte OperationCode.GetProperties = (byte)251`

(251) Get Properties

8.26.2.10 `const byte OperationCode.GetRegions = 220`

(220) Get list of regional servers from a NameServer.

8.26.2.11 `const byte OperationCode.Join = 255`

(255) Code for OpJoin, to get into a room.

8.26.2.12 `const byte OperationCode.JoinGame = 226`

(226) Join game (by name)

8.26.2.13 `const byte OperationCode.JoinLobby = 229`

(229) Joins lobby (on master)

8.26.2.14 `const byte OperationCode.JoinRandomGame = 225`

(225) Joins random game (on master)

8.26.2.15 `const byte OperationCode.Leave = (byte)254`

(254) Code for OpLeave, to get out of a room.

8.26.2.16 `const byte OperationCode.LeaveLobby = 228`

(228) Leaves lobby (on master)

8.26.2.17 `const byte OperationCode.RaiseEvent = (byte)253`

(253) Raise event (in a room, for other actors/players)

8.26.2.18 `const byte OperationCode.ServerSettings = 218`

(218) Operation to set some server settings. Used with different parameters on various servers.

8.26.2.19 `const byte OperationCode.SetProperties = (byte)252`

(252) Set Properties (of room or actor/player)

8.26.2.20 `const byte OperationCode.WebRpc = 219`

(219) WebRpc Operation.

8.27 ExitGames.Client.Photon.Chat.ParameterCode Class Reference

Public Attributes

- `const byte ApplicationId = 224`
- `const byte Secret = 221`
(221) Internally used to establish encryption
- `const byte AppVersion = 220`
- `const byte ClientAuthenticationType = 217`
(217) This key's (byte) value defines the target custom authentication type/service the client connects with. Used in OpAuthenticate
- `const byte ClientAuthenticationParams = 216`
(216) This key's (string) value provides parameters sent to the custom authentication type/service the client connects with. Used in OpAuthenticate
- `const byte ClientAuthenticationData = 214`
(214) This key's (string or byte[]) value provides parameters sent to the custom authentication service setup in Photon Dashboard. Used in OpAuthenticate
- `const byte Region = 210`
(210) Used for region values in OpAuth and OpGetRegions.
- `const byte Address = 230`
(230) Address of a (game) server to use.
- `const byte UserId = 225`
(225) User's ID

8.27.1 Member Data Documentation

8.27.1.1 `const byte ExitGames.Client.Photon.Chat.ParameterCode.Address = 230`

(230) Address of a (game) server to use.

8.27.1.2 `const byte ExitGames.Client.Photon.Chat.ParameterCode.ApplicationId = 224`

8.27.1.3 `const byte ExitGames.Client.Photon.Chat.ParameterCode.AppVersion = 220`

8.27.1.4 `const byte ExitGames.Client.Photon.Chat.ParameterCode.ClientAuthenticationData = 214`

(214) This key's (string or byte[]) value provides parameters sent to the custom authentication service setup in [Photon](#) Dashboard. Used in `OpAuthenticate`

8.27.1.5 `const byte ExitGames.Client.Photon.Chat.ParameterCode.ClientAuthenticationParams = 216`

(216) This key's (string) value provides parameters sent to the custom authentication type/service the client connects with. Used in `OpAuthenticate`

8.27.1.6 `const byte ExitGames.Client.Photon.Chat.ParameterCode.ClientAuthenticationType = 217`

(217) This key's (byte) value defines the target custom authentication type/service the client connects with. Used in `OpAuthenticate`

8.27.1.7 `const byte ExitGames.Client.Photon.Chat.ParameterCode.Region = 210`

(210) Used for region values in `OpAuth` and `OpGetRegions`.

8.27.1.8 `const byte ExitGames.Client.Photon.Chat.ParameterCode.Secret = 221`

(221) Internally used to establish encryption

8.27.1.9 `const byte ExitGames.Client.Photon.Chat.ParameterCode.UserId = 225`

(225) User's ID

8.28 ParameterCode Class Reference

Class for constants. Codes for parameters of Operations and Events.

Public Attributes

- `const byte SuppressRoomEvents = 237`
(237) A bool parameter for creating games. If set to true, no room events are sent to the clients on join and leave. Default: false (and not sent).
- `const byte EmptyRoomTTL = 236`
(236) Time To Live (TTL) for a room when the last player leaves. Keeps room in memory for case a player re-joins soon. In milliseconds.
- `const byte PlayerTTL = 235`

- (235) Time To Live (TTL) for an 'actor' in a room. If a client disconnects, this actor is inactive first and removed after this timeout. In milliseconds.

 - const byte [EventForward](#) = 234

(234) Optional parameter of `OpRaiseEvent` and `OpSetCustomProperties` to forward the event/operation to a web-service.
- const byte [IsComingBack](#) = (byte)233

(233) Optional parameter of `OpLeave` in async games. If false, the player does abandons the game (forever). By default players become inactive and can re-join.
- const byte [IsInactive](#) = (byte)233

(233) Used in `EvLeave` to describe if a user is inactive (and might come back) or not. In rooms with `PlayerTTL`, becoming inactive is the default case.
- const byte [CheckUserOnJoin](#) = (byte)232

(232) Used when creating rooms to define if any userid can join the room only once.
- const byte [ExpectedValues](#) = (byte)231

(231) Code for "Check And Swap" (CAS) when changing properties.
- const byte [Address](#) = 230

(230) Address of a (game) server to use.
- const byte [PeerCount](#) = 229

(229) Count of players in this application in a rooms (used in stats event)
- const byte [GameCount](#) = 228

(228) Count of games in this application (used in stats event)
- const byte [MasterPeerCount](#) = 227

(227) Count of players on the master server (in this app, looking for rooms)
- const byte [UserId](#) = 225

(225) User's ID
- const byte [ApplicationId](#) = 224

(224) Your application's ID: a name on your own [Photon](#) or a GUID on the [Photon](#) Cloud
- const byte [Position](#) = 223

(223) Not used currently (as "Position"). If you get queued before connect, this is your position
- const byte [MatchMakingType](#) = 223

(223) Modifies the matchmaking algorithm used for `OpJoinRandom`. Allowed parameter values are defined in enum `MatchmakingMode`.
- const byte [GameList](#) = 222

(222) List of `RoomInfos` about open / listed rooms
- const byte [Secret](#) = 221

(221) Internally used to establish encryption
- const byte [AppVersion](#) = 220

(220) Version of your application
- const byte [AzureNodeInfo](#) = 210

(210) Internally used in case of hosting by Azure
- const byte [AzureLocalNodeId](#) = 209

(209) Internally used in case of hosting by Azure
- const byte [AzureMasterNodeId](#) = 208

(208) Internally used in case of hosting by Azure
- const byte [RoomName](#) = (byte)255

(255) Code for the `gameId/roomName` (a unique name per room). Used in `OpJoin` and similar.
- const byte [Broadcast](#) = (byte)250

(250) Code for broadcast parameter of `OpSetProperties` method.
- const byte [ActorList](#) = (byte)252

(252) Code for list of players in a room. Currently not used.
- const byte [ActorNr](#) = (byte)254

(254) Code of the Actor of an operation. Used for property get and set.

- const byte [PlayerProperties](#) = (byte)249
(249) Code for property set (Hashtable).
- const byte [CustomEventContent](#) = (byte)245
(245) Code of data/custom content of an event. Used in *OpRaiseEvent*.
- const byte [Data](#) = (byte)245
(245) Code of data of an event. Used in *OpRaiseEvent*.
- const byte [Code](#) = (byte)244
(244) Code used when sending some code-related parameter, like *OpRaiseEvent*'s event-code.
- const byte [GameProperties](#) = (byte)248
(248) Code for property set (Hashtable).
- const byte [Properties](#) = (byte)251
(251) Code for property-set (Hashtable). This key is used when sending only one set of properties. If either [Actor→Properties](#) or [GameProperties](#) are used (or both), check those keys.
- const byte [TargetActorNr](#) = (byte)253
(253) Code of the target Actor of an operation. Used for property set. Is 0 for game
- const byte [ReceiverGroup](#) = (byte)246
(246) Code to select the receivers of events (used in *Lite*, *Operation RaiseEvent*).
- const byte [Cache](#) = (byte)247
(247) Code for caching events while raising them.
- const byte [CleanupCacheOnLeave](#) = (byte)241
(241) Bool parameter of *CreateRoom* Operation. If true, server cleans up roomcache of leaving players (their cached events get removed).
- const byte [Group](#) = 240
(240) Code for "group" operation-parameter (as used in *Op RaiseEvent*).
- const byte [Remove](#) = 239
(239) The "Remove" operation-parameter can be used to remove something from a list. E.g. remove groups from player's interest groups.
- const byte [PublishUserId](#) = 239
(239) Used in *Op Join* to define if UserIds of the players are broadcast in the room. Useful for *FindFriends* and reserving slots for expected users.
- const byte [Add](#) = 238
(238) The "Add" operation-parameter can be used to add something to some list or set. E.g. add groups to player's interest groups.
- const byte [Info](#) = 218
(218) Content for [EventCode.ErrorInfo](#) and internal debug operations.
- const byte [ClientAuthenticationType](#) = 217
(217) This key's (byte) value defines the target custom authentication type/service the client connects with. Used in *OpAuthenticate*
- const byte [ClientAuthenticationParams](#) = 216
(216) This key's (string) value provides parameters sent to the custom authentication type/service the client connects with. Used in *OpAuthenticate*
- const byte [JoinMode](#) = 215
(215) Makes the server create a room if it doesn't exist. *OpJoin* uses this to always enter a room, unless it exists and is full/closed.
- const byte [ClientAuthenticationData](#) = 214
(214) This key's (string or byte[]) value provides parameters sent to the custom authentication service setup in [Photon Dashboard](#). Used in *OpAuthenticate*
- const byte [MasterClientId](#) = (byte)203
(203) Code for *MasterClientId*, which is synced by server. When sent as op-parameter this is code 203.
- const byte [FindFriendsRequestList](#) = (byte)1
(1) Used in *Op FindFriends* request. Value must be string[] of friends to look up.
- const byte [FindFriendsResponseOnlineList](#) = (byte)1

- (1) Used in Op FindFriends response. Contains bool[] list of online states (false if not online).

 - const byte [FindFriendsResponseRoomIdList](#) = (byte)2
- (2) Used in Op FindFriends response. Contains string[] of room names ("" where not known or no room joined).

 - const byte [LobbyName](#) = (byte)213
- (213) Used in matchmaking-related methods and when creating a room to name a lobby (to join or to attach a room to).

 - const byte [LobbyType](#) = (byte)212
- (212) Used in matchmaking-related methods and when creating a room to define the type of a lobby. Combined with the lobby name this identifies the lobby.

 - const byte [LobbyStats](#) = (byte)211
- (211) This (optional) parameter can be sent in Op Authenticate to turn on Lobby Stats (info about lobby names and their user- and game-counts). See: [PhotonNetwork.Lobbies](#)

 - const byte [Region](#) = (byte)210
- (210) Used for region values in OpAuth and OpGetRegions.

 - const byte [UriPath](#) = 209
- (209) Path of the WebRPC that got called. Also known as "WebRpc Name". Type: string.

 - const byte [WebRpcParameters](#) = 208
- (208) Parameters for a WebRPC as: Dictionary<string, object>. This will get serialized to JSON.

 - const byte [WebRpcReturnCode](#) = 207
- (207) ReturnCode for the WebRPC, as sent by the web service (not by [Photon](#), which uses [ErrorCode](#)). Type: byte.

 - const byte [WebRpcReturnMessage](#) = 206
- (206) Message returned by WebRPC server. Analog to [Photon](#)'s debug message. Type: string.

 - const byte [CacheSliceIndex](#) = 205
- (205) Used to define a "slice" for cached events. Slices can easily be removed from cache. Type: int.

 - const byte [Plugins](#) = 204
- (204) Informs the server of the expected plugin setup.

 - const byte [NickName](#) = 202
- (202) Used by the server in Operation Responses, when it sends the nickname of the client (the user's nickname).

 - const byte [PluginName](#) = 201
- (201) Informs user about name of plugin load to game

 - const byte [PluginVersion](#) = 200
- (200) Informs user about version of plugin load to game

 - const byte [ExpectedProtocol](#) = 195
- (195) Protocol which will be used by client to connect master/game servers. Used for nameserver.

 - const byte [CustomInitData](#) = 194
- (194) Set of custom parameters which are sent in auth request.

 - const byte [EncryptionMode](#) = 193
- (193) How are we going to encrypt data.

 - const byte [EncryptionData](#) = 192
- (192) Parameter of Authentication, which contains encryption keys (depends on AuthMode and EncryptionMode).

 - const byte [RoomOptionFlags](#) = 191
- (191) An int parameter summarizing several boolean room-options with bit-flags.

8.28.1 Detailed Description

Class for constants. Codes for parameters of Operations and Events.

Pun uses these constants internally.

8.28.2 Member Data Documentation

8.28.2.1 `const byte ParameterCode.ActorList = (byte)252`

(252) Code for list of players in a room. Currently not used.

8.28.2.2 `const byte ParameterCode.ActorNr = (byte)254`

(254) Code of the Actor of an operation. Used for property get and set.

8.28.2.3 `const byte ParameterCode.Add = 238`

(238) The "Add" operation-parameter can be used to add something to some list or set. E.g. add groups to player's interest groups.

8.28.2.4 `const byte ParameterCode.Address = 230`

(230) Address of a (game) server to use.

8.28.2.5 `const byte ParameterCode.ApplicationId = 224`

(224) Your application's ID: a name on your own [Photon](#) or a GUID on the [Photon](#) Cloud

8.28.2.6 `const byte ParameterCode.AppVersion = 220`

(220) Version of your application

8.28.2.7 `const byte ParameterCode.AzureLocalNodeId = 209`

(209) Internally used in case of hosting by Azure

8.28.2.8 `const byte ParameterCode.AzureMasterNodeId = 208`

(208) Internally used in case of hosting by Azure

8.28.2.9 `const byte ParameterCode.AzureNodeInfo = 210`

(210) Internally used in case of hosting by Azure

8.28.2.10 `const byte ParameterCode.Broadcast = (byte)250`

(250) Code for broadcast parameter of `OpSetProperties` method.

8.28.2.11 `const byte ParameterCode.Cache = (byte)247`

(247) Code for caching events while raising them.

8.28.2.12 `const byte ParameterCode.CacheSliceIndex = 205`

(205) Used to define a "slice" for cached events. Slices can easily be removed from cache. Type: `int`.

8.28.2.13 const byte ParameterCode.CheckUserOnJoin = (byte)232

(232) Used when creating rooms to define if any userid can join the room only once.

8.28.2.14 const byte ParameterCode.CleanupCacheOnLeave = (byte)241

(241) Bool parameter of CreateRoom Operation. If true, server cleans up roomcache of leaving players (their cached events get removed).

8.28.2.15 const byte ParameterCode.ClientAuthenticationData = 214

(214) This key's (string or byte[]) value provides parameters sent to the custom authentication service setup in [Photon](#) Dashboard. Used in OpAuthenticate

8.28.2.16 const byte ParameterCode.ClientAuthenticationParams = 216

(216) This key's (string) value provides parameters sent to the custom authentication type/service the client connects with. Used in OpAuthenticate

8.28.2.17 const byte ParameterCode.ClientAuthenticationType = 217

(217) This key's (byte) value defines the target custom authentication type/service the client connects with. Used in OpAuthenticate

8.28.2.18 const byte ParameterCode.Code = (byte)244

(244) Code used when sending some code-related parameter, like OpRaiseEvent's event-code.

This is not the same as the Operation's code, which is no longer sent as part of the parameter Dictionary in [Photon](#) 3.

8.28.2.19 const byte ParameterCode.CustomEventContent = (byte)245

(245) Code of data/custom content of an event. Used in OpRaiseEvent.

8.28.2.20 const byte ParameterCode.CustomInitData = 194

(194) Set of custom parameters which are sent in auth request.

8.28.2.21 const byte ParameterCode.Data = (byte)245

(245) Code of data of an event. Used in OpRaiseEvent.

8.28.2.22 const byte ParameterCode.EmptyRoomTTL = 236

(236) Time To Live (TTL) for a room when the last player leaves. Keeps room in memory for case a player re-joins soon. In milliseconds.

8.28.2.23 const byte ParameterCode.EncryptionData = 192

(192) Parameter of Authentication, which contains encryption keys (depends on AuthMode and EncryptionMode).

8.28.2.24 const byte ParameterCode.EncryptionMode = 193

(193) How are we going to encrypt data.

8.28.2.25 const byte ParameterCode.EventForward = 234

(234) Optional parameter of OpRaiseEvent and OpSetCustomProperties to forward the event/operation to a web-service.

8.28.2.26 const byte ParameterCode.ExpectedProtocol = 195

(195) Protocol which will be used by client to connect master/game servers. Used for nameserver.

8.28.2.27 const byte ParameterCode.ExpectedValues = (byte)231

(231) Code for "Check And Swap" (CAS) when changing properties.

8.28.2.28 const byte ParameterCode.FindFriendsRequestList = (byte)1

(1) Used in Op FindFriends request. Value must be string[] of friends to look up.

8.28.2.29 const byte ParameterCode.FindFriendsResponseOnlineList = (byte)1

(1) Used in Op FindFriends response. Contains bool[] list of online states (false if not online).

8.28.2.30 const byte ParameterCode.FindFriendsResponseRoomIdList = (byte)2

(2) Used in Op FindFriends response. Contains string[] of room names ("" where not known or no room joined).

8.28.2.31 const byte ParameterCode.GameCount = 228

(228) Count of games in this application (used in stats event)

8.28.2.32 const byte ParameterCode.GameList = 222

(222) List of RoomInfos about open / listed rooms

8.28.2.33 const byte ParameterCode.GameProperties = (byte)248

(248) Code for property set (Hashtable).

8.28.2.34 const byte ParameterCode.Group = 240

(240) Code for "group" operation-parameter (as used in Op RaiseEvent).

8.28.2.35 const byte ParameterCode.Info = 218

(218) Content for [EventCode.ErrorInfo](#) and internal debug operations.

8.28.2.36 const byte ParameterCode.IsComingBack = (byte)233

(233) Optional parameter of OpLeave in async games. If false, the player does abandons the game (forever). By default players become inactive and can re-join.

8.28.2.37 const byte ParameterCode.IsInactive = (byte)233

(233) Used in EvLeave to describe if a user is inactive (and might come back) or not. In rooms with PlayerTTL, becoming inactive is the default case.

8.28.2.38 const byte ParameterCode.JoinMode = 215

(215) Makes the server create a room if it doesn't exist. OpJoin uses this to always enter a room, unless it exists and is full/closed.

(215) The JoinMode enum defines which variant of joining a room will be executed: Join only if available, create if not exists or re-join.

Replaces CreateIfNotExists which was only a bool-value.

8.28.2.39 const byte ParameterCode.LobbyName = (byte)213

(213) Used in matchmaking-related methods and when creating a room to name a lobby (to join or to attach a room to).

8.28.2.40 const byte ParameterCode.LobbyStats = (byte)211

(211) This (optional) parameter can be sent in Op Authenticate to turn on Lobby Stats (info about lobby names and their user- and game-counts). See: PhotonNetwork.Lobbies

8.28.2.41 const byte ParameterCode.LobbyType = (byte)212

(212) Used in matchmaking-related methods and when creating a room to define the type of a lobby. Combined with the lobby name this identifies the lobby.

8.28.2.42 const byte ParameterCode.MasterClientId = (byte)203

(203) Code for MasterClientId, which is synced by server. When sent as op-parameter this is code 203.

Tightly related to [GamePropertyKey.MasterClientId](#).

8.28.2.43 const byte ParameterCode.MasterPeerCount = 227

(227) Count of players on the master server (in this app, looking for rooms)

8.28.2.44 const byte ParameterCode.MatchMakingType = 223

(223) Modifies the matchmaking algorithm used for OpJoinRandom. Allowed parameter values are defined in enum MatchmakingMode.

8.28.2.45 const byte ParameterCode.NickName = 202

(202) Used by the server in Operation Responses, when it sends the nickname of the client (the user's nickname).

8.28.2.46 `const byte ParameterCode.PeerCount = 229`

(229) Count of players in this application in a rooms (used in stats event)

8.28.2.47 `const byte ParameterCode.PlayerProperties = (byte)249`

(249) Code for property set (Hashtable).

8.28.2.48 `const byte ParameterCode.PlayerTTL = 235`

(235) Time To Live (TTL) for an 'actor' in a room. If a client disconnects, this actor is inactive first and removed after this timeout. In milliseconds.

8.28.2.49 `const byte ParameterCode.PluginName = 201`

(201) Informs user about name of plugin load to game

8.28.2.50 `const byte ParameterCode.Plugins = 204`

(204) Informs the server of the expected plugin setup.

The operation will fail in case of a plugin mismatch returning error code `PluginMismatch 32751 (0x7FFF - 16)`. Setting `string[]{}` means the client expects no plugin to be setup. Note: for backwards compatibility null omits any check.

8.28.2.51 `const byte ParameterCode.PluginVersion = 200`

(200) Informs user about version of plugin load to game

8.28.2.52 `const byte ParameterCode.Position = 223`

(223) Not used currently (as "Position"). If you get queued before connect, this is your position

8.28.2.53 `const byte ParameterCode.Properties = (byte)251`

(251) Code for property-set (Hashtable). This key is used when sending only one set of properties. If either [Actor↔ Properties](#) or `GameProperties` are used (or both), check those keys.

8.28.2.54 `const byte ParameterCode.PublishUserId = 239`

(239) Used in Op Join to define if UserIds of the players are broadcast in the room. Useful for FindFriends and reserving slots for expected users.

8.28.2.55 `const byte ParameterCode.ReceiverGroup = (byte)246`

(246) Code to select the receivers of events (used in Lite, Operation RaiseEvent).

8.28.2.56 `const byte ParameterCode.Region = (byte)210`

(210) Used for region values in OpAuth and OpGetRegions.

8.28.2.57 const byte ParameterCode.Remove = 239

(239) The "Remove" operation-parameter can be used to remove something from a list. E.g. remove groups from player's interest groups.

8.28.2.58 const byte ParameterCode.RoomName = (byte)255

(255) Code for the gameId/roomName (a unique name per room). Used in OpJoin and similar.

8.28.2.59 const byte ParameterCode.RoomOptionFlags = 191

(191) An int parameter summarizing several boolean room-options with bit-flags.

8.28.2.60 const byte ParameterCode.Secret = 221

(221) Internally used to establish encryption

8.28.2.61 const byte ParameterCode.SuppressRoomEvents = 237

(237) A bool parameter for creating games. If set to true, no room events are sent to the clients on join and leave. Default: false (and not sent).

8.28.2.62 const byte ParameterCode.TargetActorNr = (byte)253

(253) Code of the target Actor of an operation. Used for property set. Is 0 for game

8.28.2.63 const byte ParameterCode.UriPath = 209

(209) Path of the WebRPC that got called. Also known as "WebRpc Name". Type: string.

8.28.2.64 const byte ParameterCode.UserId = 225

(225) User's ID

8.28.2.65 const byte ParameterCode.WebRpcParameters = 208

(208) Parameters for a WebRPC as: Dictionary<string, object>. This will get serialized to JSON.

8.28.2.66 const byte ParameterCode.WebRpcReturnCode = 207

(207) ReturnCode for the WebRPC, as sent by the web service (not by [Photon](#), which uses [ErrorCode](#)). Type: byte.

8.28.2.67 const byte ParameterCode.WebRpcReturnMessage = 206

(206) Message returned by WebRPC server. Analog to [Photon](#)'s debug message. Type: string.

8.29 PhotonAnimatorView Class Reference

This class helps you to synchronize Mecanim animations. Simply add the component to your GameObject and make sure that the [PhotonAnimatorView](#) is added to the list of observed components.

Inherits [MonoBehaviour](#), and [IPunObservable](#).

Classes

- class [SynchronizedLayer](#)
- class [SynchronizedParameter](#)

Public Types

- enum [ParameterType](#) { [ParameterType.Float](#) = 1, [ParameterType.Int](#) = 3, [ParameterType.Bool](#) = 4, [ParameterType.Trigger](#) = 9 }
- enum [SynchronizeType](#) { [SynchronizeType.Disabled](#) = 0, [SynchronizeType.Discrete](#) = 1, [SynchronizeType.Continuous](#) = 2 }

Public Member Functions

- void [CacheDiscreteTriggers](#) ()
Caches the discrete triggers values for keeping track of raised triggers, and will be reseted after the sync routine got performed
- bool [DoesLayerSynchronizeTypeExist](#) (int layerIndex)
Check if a specific layer is configured to be synchronize
- bool [DoesParameterSynchronizeTypeExist](#) (string name)
Check if the specified parameter is configured to be synchronized
- List< [SynchronizedLayer](#) > [GetSynchronizedLayers](#) ()
Get a list of all synchronized layers
- List< [SynchronizedParameter](#) > [GetSynchronizedParameters](#) ()
Get a list of all synchronized parameters
- [SynchronizeType](#) [GetLayerSynchronizeType](#) (int layerIndex)
Gets the type how the layer is synchronized
- [SynchronizeType](#) [GetParameterSynchronizeType](#) (string name)
Gets the type how the parameter is synchronized
- void [SetLayerSynchronized](#) (int layerIndex, [SynchronizeType](#) synchronizeType)
Sets the how a layer should be synchronized
- void [SetParameterSynchronized](#) (string name, [ParameterType](#) type, [SynchronizeType](#) synchronizeType)
Sets the how a parameter should be synchronized
- void [OnPhotonSerializeView](#) ([PhotonStream](#) stream, [PhotonMessageInfo](#) info)
Called by PUN several times per second, so that your script can write and read synchronization data for the [PhotonAnimatorView](#).

8.29.1 Detailed Description

This class helps you to synchronize Mecanim animations. Simply add the component to your GameObject and make sure that the [PhotonAnimatorView](#) is added to the list of observed components.

When Using Trigger Parameters, make sure the component that sets the trigger is higher in the stack of Components on the GameObject than '[PhotonAnimatorView](#)'. Triggers are raised true during one frame only.

8.29.2 Member Enumeration Documentation

8.29.2.1 enum PhotonAnimatorView.ParameterType

Enumerator

Float

Int

Bool

Trigger

8.29.2.2 enum PhotonAnimatorView.SynchronizeType

Enumerator

Disabled

Discrete

Continuous

8.29.3 Member Function Documentation

8.29.3.1 void PhotonAnimatorView.CacheDiscreteTriggers ()

Caches the discrete triggers values for keeping track of raised triggers, and will be reseted after the sync routine got performed

8.29.3.2 bool PhotonAnimatorView.DoesLayerSynchronizeTypeExist (int *layerIndex*)

Check if a specific layer is configured to be synchronize

Parameters

<i>layerIndex</i>	Index of the layer.
-------------------	---------------------

Returns

True if the layer is synchronized

8.29.3.3 bool PhotonAnimatorView.DoesParameterSynchronizeTypeExist (string *name*)

Check if the specified parameter is configured to be synchronized

Parameters

<i>name</i>	The name of the parameter.
-------------	----------------------------

Returns

True if the parameter is synchronized

8.29.3.4 SynchronizeType PhotonAnimatorView.GetLayerSynchronizeType (int *layerIndex*)

Gets the type how the layer is synchronized

Parameters

<i>layerIndex</i>	Index of the layer.
-------------------	---------------------

Returns

Disabled/Discrete/Continuous

8.29.3.5 **SynchronizeType** PhotonAnimatorView.GetParameterSynchronizeType (string *name*)

Gets the type how the parameter is synchronized

Parameters

<i>name</i>	The name of the parameter.
-------------	----------------------------

Returns

Disabled/Discrete/Continuous

8.29.3.6 **List<SynchronizedLayer>** PhotonAnimatorView.GetSynchronizedLayers ()

Get a list of all synchronized layers

Returns

List of [SynchronizedLayer](#) objects

8.29.3.7 **List<SynchronizedParameter>** PhotonAnimatorView.GetSynchronizedParameters ()

Get a list of all synchronized parameters

Returns

List of [SynchronizedParameter](#) objects

8.29.3.8 **void** PhotonAnimatorView.OnPhotonSerializeView ([PhotonStream](#) *stream*, [PhotonMessageInfo](#) *info*)

Called by PUN several times per second, so that your script can write and read synchronization data for the [PhotonView](#).

This method will be called in scripts that are assigned as Observed component of a [PhotonView](#).

[PhotonNetwork.sendRateOnSerialize](#) affects how often this method is called.

[PhotonNetwork.sendRate](#) affects how often packages are sent by this client.

Implementing this method, you can customize which data a [PhotonView](#) regularly synchronizes. Your code defines what is being sent (content) and how your data is used by receiving clients.

Unlike other callbacks, *OnPhotonSerializeView* only gets called when it is assigned to a [PhotonView](#) as [PhotonView.observed](#) script.

To make use of this method, the [PhotonStream](#) is essential. It will be in "writing" mode" on the client that controls a [PhotonView](#) ([PhotonStream.isWriting](#) == true) and in "reading mode" on the remote clients that just receive that the controlling client sends.

If you skip writing any value into the stream, PUN will skip the update. Used carefully, this can conserve bandwidth and messages (which have a limit per room/second).

Note that `OnPhotonSerializeView` is not called on remote clients when the sender does not send any update. This can't be used as "x-times per second Update()".

Implements [IPunObservable](#).

8.29.3.9 void PhotonAnimatorView.SetLayerSynchronized (int *layerIndex*, SynchronizeType *synchronizeType*)

Sets the how a layer should be synchronized

Parameters

<i>layerIndex</i>	Index of the layer.
<i>synchronizeType</i>	Disabled/Discrete/Continuous

8.29.3.10 void PhotonAnimatorView.SetParameterSynchronized (string *name*, ParameterType *type*, SynchronizeType *synchronizeType*)

Sets the how a parameter should be synchronized

Parameters

<i>name</i>	The name of the parameter.
<i>type</i>	The type of the parameter.
<i>synchronizeType</i>	Disabled/Discrete/Continuous

8.30 PhotonLagSimulationGui Class Reference

This `MonoBehaviour` is a basic GUI for the [Photon](#) client's network-simulation feature. It can modify lag (fixed delay), jitter (random lag) and packet loss.

Inherits `MonoBehaviour`.

Public Member Functions

- void [Start](#) ()
- void [OnGUI](#) ()

Public Attributes

- Rect [WindowRect](#) = new Rect(0, 100, 120, 100)
Positioning rect for window.
- int [WindowId](#) = 101
Unity GUI Window ID (must be unique or will cause issues).
- bool [Visible](#) = true
Shows or hides GUI (does not affect settings).

Properties

- PhotonPeer [Peer](#) [get, set]
The peer currently in use (to set the network simulation).

8.30.1 Detailed Description

This MonoBehaviour is a basic GUI for the [Photon](#) client's network-simulation feature. It can modify lag (fixed delay), jitter (random lag) and packet loss.

8.30.2 Member Function Documentation

8.30.2.1 void PhotonLagSimulationGui.OnGUI ()

8.30.2.2 void PhotonLagSimulationGui.Start ()

8.30.3 Member Data Documentation

8.30.3.1 bool PhotonLagSimulationGui.Visible = true

Shows or hides GUI (does not affect settings).

8.30.3.2 int PhotonLagSimulationGui.WindowId = 101

Unity GUI Window ID (must be unique or will cause issues).

8.30.3.3 Rect PhotonLagSimulationGui.WindowRect = new Rect(0, 100, 120, 100)

Positioning rect for window.

8.30.4 Property Documentation

8.30.4.1 PhotonPeer PhotonLagSimulationGui.Peer [get], [set]

The peer currently in use (to set the network simulation).

8.31 PhotonMessageInfo Struct Reference

Container class for info about a particular message, RPC or update.

Public Member Functions

- [PhotonMessageInfo](#) ([PhotonPlayer](#) player, int timestamp, [PhotonView](#) view)
- override string [ToString](#) ()

Public Attributes

- readonly [PhotonPlayer](#) sender
- readonly [PhotonView](#) photonView

Properties

- double [timestamp](#) [get]

8.31.1 Detailed Description

Container class for info about a particular message, RPC or update.

8.31.2 Constructor & Destructor Documentation

8.31.2.1 `PhotonMessageInfo.PhotonMessageInfo (PhotonPlayer player, int timestamp, PhotonView view)`

8.31.3 Member Function Documentation

8.31.3.1 `override string PhotonMessageInfo.ToString ()`

8.31.4 Member Data Documentation

8.31.4.1 `readonly PhotonView PhotonMessageInfo.photonView`

8.31.4.2 `readonly PhotonPlayer PhotonMessageInfo.sender`

8.31.5 Property Documentation

8.31.5.1 `double PhotonMessageInfo.timestamp [get]`

8.32 PhotonNetwork Class Reference

The main class to use the [PhotonNetwork](#) plugin. This class is static.

Public Member Functions

- delegate void [EventCallback](#) (byte eventCode, object content, int senderId)
Defines the delegate usable in OnEventCall.

Static Public Member Functions

- static void [SwitchToProtocol](#) (ConnectionProtocol cp)
While offline, the network protocol can be switched (which affects the ports you can use to connect).
- static bool [ConnectUsingSettings](#) (string gameVersion)
Connect to [Photon](#) as configured in the editor (saved in PhotonServerSettings file).
- static bool [ConnectToMaster](#) (string masterServerAddress, int port, string appId, string gameVersion)
Connect to a [Photon](#) Master Server by address, port, appId and game(client) version.
- static bool [Reconnect](#) ()
Can be used to reconnect to the master server after a disconnect.
- static bool [ReconnectAndRejoin](#) ()
When the client lost connection during gameplay, this method attempts to reconnect and rejoin the room.
- static bool [ConnectToBestCloudServer](#) (string gameVersion)
Connect to the [Photon](#) Cloud region with the lowest ping (on platforms that support Unity's Ping).
- static bool [ConnectToRegion](#) (CloudRegionCode region, string gameVersion)
Connects to the [Photon](#) Cloud region of choice.
- static void [OverrideBestCloudServer](#) (CloudRegionCode region)
Overwrites the region that is used for [ConnectToBestCloudServer\(string gameVersion\)](#).
- static void [RefreshCloudServerRating](#) ()
Pings all cloud servers again to find the one with best ping (currently).

- static void [NetworkStatisticsReset](#) ()
Resets the traffic stats and re-enables them.
- static string [NetworkStatisticsToString](#) ()
Only available when [NetworkStatisticsEnabled](#) was used to gather some stats.
- static void [InitializeSecurity](#) ()
Used for compatibility with Unity networking only. Encryption is automatically initialized while connecting.
- static void [Disconnect](#) ()
*Makes this client disconnect from the photon server, a process that leaves any room and calls [OnDisconnected](#)←
FromPhoton on completion.*
- static bool [FindFriends](#) (string[] friendsToFind)
Requests the rooms and online status for a list of friends and saves the result in [PhotonNetwork.Friends](#).
- static bool [CreateRoom](#) (string roomName)
Creates a room with given name but fails if this room(name) is existing already. Creates random name for roomName null.
- static bool [CreateRoom](#) (string roomName, [RoomOptions](#) roomOptions, [TypedLobby](#) typedLobby)
Creates a room but fails if this room is existing already. Can only be called on Master Server.
- static bool [CreateRoom](#) (string roomName, [RoomOptions](#) roomOptions, [TypedLobby](#) typedLobby, string[] expectedUsers)
Creates a room but fails if this room is existing already. Can only be called on Master Server.
- static bool [JoinRoom](#) (string roomName)
Join room by roomname and on success calls [OnJoinedRoom\(\)](#). This is not affected by lobbies.
- static bool [JoinRoom](#) (string roomName, string[] expectedUsers)
Join room by roomname and on success calls [OnJoinedRoom\(\)](#). This is not affected by lobbies.
- static bool [JoinOrCreateRoom](#) (string roomName, [RoomOptions](#) roomOptions, [TypedLobby](#) typedLobby)
Lets you either join a named room or create it on the fly - you don't have to know if someone created the room already.
- static bool [JoinOrCreateRoom](#) (string roomName, [RoomOptions](#) roomOptions, [TypedLobby](#) typedLobby, string[] expectedUsers)
Lets you either join a named room or create it on the fly - you don't have to know if someone created the room already.
- static bool [JoinRandomRoom](#) ()
Joins any available room of the currently used lobby and fails if none is available.
- static bool [JoinRandomRoom](#) ([Hashtable](#) expectedCustomRoomProperties, byte expectedMaxPlayers)
Attempts to join an open room with fitting, custom properties but fails if none is currently available.
- static bool [JoinRandomRoom](#) ([Hashtable](#) expectedCustomRoomProperties, byte expectedMaxPlayers, [MatchmakingMode](#) matchingType, [TypedLobby](#) typedLobby, string sqlLobbyFilter, string[] expected←
Users=null)
Attempts to join an open room with fitting, custom properties but fails if none is currently available.
- static bool [ReJoinRoom](#) (string roomName)
Can be used to return to a room after a disconnect and reconnect.
- static bool [JoinLobby](#) ()
On MasterServer this joins the default lobby which list rooms currently in use.
- static bool [JoinLobby](#) ([TypedLobby](#) typedLobby)
On a Master Server you can join a lobby to get lists of available rooms.
- static bool [LeaveLobby](#) ()
Leave a lobby to stop getting updates about available rooms.
- static bool [LeaveRoom](#) ()
Leave the current room and return to the Master Server where you can join or create rooms (see remarks).
- static bool [GetCustomRoomList](#) ([TypedLobby](#) typedLobby, string sqlLobbyFilter)
*Fetches a custom list of games from the server, matching a SQL-like "where" clause, then triggers [OnReceived](#)←
[RoomListUpdate](#) callback.*
- static [RoomInfo](#)[] [GetRoomList](#) ()
Gets currently known rooms as [RoomInfo](#) array. This is available and updated while in a lobby (check [insideLobby](#)).
- static void [SetPlayerCustomProperties](#) ([Hashtable](#) customProperties)

- Sets this (local) player's properties and synchronizes them to the other players (don't modify them directly).*
- static void [RemovePlayerCustomProperties](#) (string[] customPropertiesToDelete)
Locally removes Custom Properties of "this" player. Important: This does not synchronize the change! Useful when you switch rooms.
 - static bool [RaiseEvent](#) (byte eventCode, object eventContent, bool sendReliable, [RaiseEventOptions](#) options)
Sends fully customizable events in a room. Events consist of at least an [EventCode](#) (0..199) and can have content.
 - static int [AllocateViewID](#) ()
Allocates a viewID that's valid for the current/local player.
 - static int [AllocateSceneViewID](#) ()
Enables the Master Client to allocate a viewID that is valid for scene objects.
 - static void [UnAllocateViewID](#) (int viewID)
Unregister a viewID (of manually instantiated and destroyed networked objects).
 - static GameObject [Instantiate](#) (string prefabName, Vector3 position, Quaternion rotation, int group)
Instantiate a prefab over the network. This prefab needs to be located in the root of a "Resources" folder.
 - static GameObject [Instantiate](#) (string prefabName, Vector3 position, Quaternion rotation, int group, object[] data)
Instantiate a prefab over the network. This prefab needs to be located in the root of a "Resources" folder.
 - static GameObject [InstantiateSceneObject](#) (string prefabName, Vector3 position, Quaternion rotation, int group, object[] data)
Instantiate a scene-owned prefab over the network. The PhotonViews will be controllable by the MasterClient. This prefab needs to be located in the root of a "Resources" folder.
 - static int [GetPing](#) ()
The current roundtrip time to the photon server.
 - static void [FetchServerTimestamp](#) ()
Refreshes the server timestamp (async operation, takes a roundtrip).
 - static void [SendOutgoingCommands](#) ()
Can be used to immediately send the RPCs and Instantiates just called, so they are on their way to the other players.
 - static bool [CloseConnection](#) ([PhotonPlayer](#) kickPlayer)
Request a client to disconnect (KICK). Only the master client can do this
 - static bool [SetMasterClient](#) ([PhotonPlayer](#) masterClientPlayer)
Asks the server to assign another player as Master Client of your current room.
 - static void [Destroy](#) ([PhotonView](#) targetView)
Network-Destroy the GameObject associated with the [PhotonView](#), unless the [PhotonView](#) is static or not under this client's control.
 - static void [Destroy](#) (GameObject targetGo)
Network-Destroy the GameObject, unless it is static or not under this client's control.
 - static void [DestroyPlayerObjects](#) ([PhotonPlayer](#) targetPlayer)
Network-Destroy all GameObjects, PhotonViews and their RPCs of targetPlayer. Can only be called on local player (for "self") or Master Client (for anyone).
 - static void [DestroyPlayerObjects](#) (int targetPlayerId)
Network-Destroy all GameObjects, PhotonViews and their RPCs of this player (by ID). Can only be called on local player (for "self") or Master Client (for anyone).
 - static void [DestroyAll](#) ()
Network-Destroy all GameObjects, PhotonViews and their RPCs in the room. Removes anything buffered from the server. Can only be called by Master Client (for anyone).
 - static void [RemoveRPCs](#) ([PhotonPlayer](#) targetPlayer)
Remove all buffered RPCs from server that were sent by targetPlayer. Can only be called on local player (for "self") or Master Client (for anyone).
 - static void [RemoveRPCs](#) ([PhotonView](#) targetPhotonView)
Remove all buffered RPCs from server that were sent via targetPhotonView. The Master Client and the owner of the targetPhotonView may call this.
 - static void [RemoveRPCsInGroup](#) (int targetGroup)

Remove all buffered RPCs from server that were sent in the targetGroup, if this is the Master Client or if this controls the individual [PhotonView](#).

- static void [CacheSendMonoMessageTargets](#) (Type type)
Populates [SendMonoMessageTargets](#) with currently existing [GameObjects](#) that have a [Component](#) of type.
- static HashSet< [GameObject](#) > [FindGameObjectsWithComponent](#) (Type type)
Finds the [GameObjects](#) with [Components](#) of a specific type (using [FindObjectsOfType](#)).
- static void [SetReceivingEnabled](#) (int group, bool enabled)
- static void [SetInterestGroups](#) (byte group, bool enabled)
Enable/disable receiving events from a given [Interest Group](#).
- static void [SetReceivingEnabled](#) (int[] enableGroups, int[] disableGroups)
- static void [SetInterestGroups](#) (byte[] disableGroups, byte[] enableGroups)
Enable/disable receiving on given [Interest Groups](#) (applied to [PhotonViews](#)).
- static void [SetSendingEnabled](#) (int group, bool enabled)
- static void [SetSendingEnabled](#) (byte group, bool enabled)
Enable/disable sending on given group (applied to [PhotonViews](#))
- static void [SetSendingEnabled](#) (int[] enableGroups, int[] disableGroups)
- static void [SetSendingEnabled](#) (byte[] disableGroups, byte[] enableGroups)
Enable/disable sending on given groups (applied to [PhotonViews](#))
- static void [SetLevelPrefix](#) (short prefix)
Sets level prefix for [PhotonViews](#) instantiated later on. Don't set it if you need only one!
- static void [LoadLevel](#) (int levelNumber)
Wraps loading a level to pause the network message-queue. Optionally syncs the loaded level in a room.
- static void [LoadLevel](#) (string levelName)
Wraps loading a level to pause the network message-queue. Optionally syncs the loaded level in a room.
- static bool [WebRpc](#) (string name, object parameters)
This operation makes [Photon](#) call your custom web-service by name (path) with the given parameters.

Public Attributes

- const string [versionPUN](#) = "1.82"
Version number of PUN. Also used in [GameVersion](#) to separate client version from each other.

Static Public Attributes

- static readonly int [MAX_VIEW_IDS](#) = 1000
The maximum number of assigned [PhotonViews](#) per player (or scene). See the [General Documentation](#) topic "[Limitations](#)" on how to raise this limitation.
- static [ServerSettings](#) [PhotonServerSettings](#) = ([ServerSettings](#))Resources.Load([PhotonNetwork.serverSettingsAssetFile](#), typeof([ServerSettings](#)))
Serialized server settings, written by the Setup Wizard for use in [ConnectUsingSettings](#).
- static bool [InstantiateInRoomOnly](#) = true
If true, [Instantiate](#) methods will check if you are in a room and fail if you are not.
- static [PhotonLogLevel](#) [logLevel](#) = [PhotonLogLevel.ErrorsOnly](#)
Network log level. Controls how verbose PUN is.
- static float [precisionForVectorSynchronization](#) = 0.000099f
The minimum difference that a [Vector2](#) or [Vector3](#) (e.g. a transforms rotation) needs to change before we send it via a [PhotonView](#)'s [OnSerialize/ObservingComponent](#).
- static float [precisionForQuaternionSynchronization](#) = 1.0f
The minimum angle that a rotation needs to change before we send it via a [PhotonView](#)'s [OnSerialize/ObservingComponent](#).
- static float [precisionForFloatSynchronization](#) = 0.01f

The minimum difference between floats before we send it via a [PhotonView](#)'s `OnSerialize/ObservingComponent`.

- static bool [UseRpcMonoBehaviourCache](#)
While enabled, the `MonoBehaviours` on which we call `RPCs` are cached, avoiding costly `GetComponent<MonoBehaviour>()` calls.
- static bool [UsePrefabCache](#) = true
While enabled (true), `Instantiate` uses [PhotonNetwork.PrefabCache](#) to keep game objects in memory (improving instantiation of the same prefab).
- static Dictionary< string, GameObject > [PrefabCache](#) = new Dictionary<string, GameObject>()
Keeps references to `GameObjects` for frequent instantiation (out of memory instead of loading the Resources).
- static HashSet< GameObject > [SendMonoMessageTargets](#)
If not null, this is the (exclusive) list of `GameObjects` that get called by `PUN SendMonoMessage()`.
- static Type [SendMonoMessageTargetType](#) = typeof(MonoBehaviour)
Defines which classes can contain `PUN Callback` implementations.
- static bool [StartRpcsAsCoroutine](#) = true
Can be used to skip starting `RPCs` as `Coroutine`, which can be a performance issue.
- static int [maxConnections](#)
Only used in `Unity Networking`. In `PUN`, set the number of players in [PhotonNetwork.CreateRoom](#).
- static float [BackgroundTimeout](#) = 60.0f
Defines how many seconds `PUN` keeps the connection, after `Unity's OnApplicationPause(true)` call. Default: 60 seconds.
- static [EventCallback OnEventCall](#)
Register your `RaiseEvent` handling methods here by using `"+="`.

Properties

- static string [gameVersion](#) [get, set]
Version string for your this build. Can be used to separate incompatible clients. Sent during connect.
- static string [ServerAddress](#) [get]
Currently used server address (no matter if master or game server).
- static [CloudRegionCode CloudRegion](#) [get]
Currently used `Cloud Region` (if any). As long as the client is not on a `Master Server` or `Game Server`, the region is not yet defined.
- static bool [connected](#) [get]
False until you connected to [Photon](#) initially. True in offline mode, while connected to any server and even while switching servers.
- static bool [connecting](#) [get]
True when you called `ConnectUsingSettings` (or similar) until the low level connection to [Photon](#) gets established.
- static bool [connectedAndReady](#) [get]
A refined version of `connected` which is true only if your connection to the server is ready to accept operations like `join`, `leave`, etc.
- static [ConnectionState connectionState](#) [get]
Simplified connection state
- static [ClientState connectionStateDetailed](#) [get]
Detailed connection state (ignorant of `PUN`, so it can be "disconnected" while switching servers).
- static [ServerConnection Server](#) [get]
The server (type) this client is currently connected or connecting to.
- static [AuthenticationValues AuthValues](#) [get, set]
A user's authentication values used during connect.
- static [Room room](#) [get]
Get the room we're currently in. Null if we aren't in any room.
- static [PhotonPlayer player](#) [get]

The local [PhotonPlayer](#). Always available and represents this player. CustomProperties can be set before entering a room and will be synced as well.

- static [PhotonPlayer](#) [masterClient](#) [get]
The Master Client of the current room or null (outside of rooms).
- static string [playerName](#) [get, set]
Set to synchronize the player's nickname with everyone in the room(s) you enter. This sets [PhotonNetwork.player.NickName](#).
- static [PhotonPlayer\[\]](#) [playerList](#) [get]
The list of players in the current room, including the local player.
- static [PhotonPlayer\[\]](#) [otherPlayers](#) [get]
The list of players in the current room, excluding the local player.
- static List< [FriendInfo](#) > [Friends](#) [get, set]
Read-only list of friends, their online status and the room they are in. Null until initialized by a FindFriends call.
- static int [FriendsListAge](#) [get]
Age of friend list info (in milliseconds). It's 0 until a friend list is fetched.
- static [IPunPrefabPool](#) [PrefabPool](#) [get, set]
An Object Pool can be used to keep and reuse instantiated object instances. It replaced Unity's default Instantiate and Destroy methods.
- static bool [offlineMode](#) [get, set]
Offline mode can be set to re-use your multiplayer code in singleplayer game modes. When this is on [PhotonNetwork](#) will not create any connections and there is near to no overhead. Mostly usefull for reusing RPC's and [PhotonNetwork.Instantiate](#)
- static bool [automaticallySyncScene](#) [get, set]
Defines if all clients in a room should load the same level as the Master Client (if that used [PhotonNetwork.LoadLevel](#)).
- static bool [autoCleanUpPlayerObjects](#) [get, set]
This setting defines per room, if network-instantiated GameObjects (with [PhotonView](#)) get cleaned up when the creator of it leaves.
- static bool [autoJoinLobby](#) [get, set]
Set in [PhotonServerSettings](#) asset. Defines if the [PhotonNetwork](#) should join the "lobby" when connected to the Master server.
- static bool [EnableLobbyStatistics](#) [get, set]
Set in [PhotonServerSettings](#) asset. Enable to get a list of active lobbies from the Master Server.
- static List< [TypedLobbyInfo](#) > [LobbyStatistics](#) [get, set]
If turned on, the Master Server will provide information about active lobbies for this application.
- static bool [insideLobby](#) [get]
True while this client is in a lobby.
- static [TypedLobby](#) [lobby](#) [get, set]
The lobby that will be used when PUN joins a lobby or creates a game.
- static int [sendRate](#) [get, set]
Defines how many times per second [PhotonNetwork](#) should send a package. If you change this, do not forget to also change 'sendRateOnSerialize'.
- static int [sendRateOnSerialize](#) [get, set]
Defines how many times per second [OnPhotonSerialize](#) should be called on [PhotonViews](#).
- static bool [isMessageQueueRunning](#) [get, set]
Can be used to pause dispatching of incoming evtents (RPCs, Instantiates and anything else incoming).
- static int [unreliableCommandsLimit](#) [get, set]
Used once per dispatch to limit unreliable commands per channel (so after a pause, many channels can still cause a lot of unreliable commands)
- static double [time](#) [get]
[Photon](#) network time, synched with the server.
- static int [ServerTimestamp](#) [get]
The current server's millisecond timestamp.
- static bool [isMasterClient](#) [get]

- Are we the master client?*

 - static bool [inRoom](#) [get]
Is true while being in a room (connectionStateDetailed == ClientState.Joined).
 - static bool [isNonMasterClientInRoom](#) [get]
True if we are in a room (client) and NOT the room's masterclient
 - static int [countOfPlayersOnMaster](#) [get]
The count of players currently looking for a room (available on MasterServer in 5sec intervals).
 - static int [countOfPlayersInRooms](#) [get]
Count of users currently playing your app in some room (sent every 5sec by Master Server). Use playerList.Count to get the count of players in the room you're in!
 - static int [countOfPlayers](#) [get]
The count of players currently using this application (available on MasterServer in 5sec intervals).
 - static int [countOfRooms](#) [get]
The count of rooms currently in use (available on MasterServer in 5sec intervals).
 - static bool [NetworkStatisticsEnabled](#) [get, set]
Enables or disables the collection of statistics about this client's traffic.
 - static int [ResentReliableCommands](#) [get]
Count of commands that got repeated (due to local repeat-timing before an ACK was received).
 - static bool [CrcCheckEnabled](#) [get, set]
Crc checks can be useful to detect and avoid issues with broken datagrams. Can be enabled while not connected.
 - static int [PacketLossByCrcCheck](#) [get]
If CrcCheckEnabled, this counts the incoming packages that don't have a valid CRC checksum and got rejected.
 - static int [MaxResendsBeforeDisconnect](#) [get, set]
Defines the number of times a reliable message can be resent before not getting an ACK for it will trigger a disconnect. Default: 5.
 - static int [QuickResends](#) [get, set]
In case of network loss, reliable messages can be repeated quickly up to 3 times.

8.32.1 Detailed Description

The main class to use the [PhotonNetwork](#) plugin. This class is static.

8.32.2 Member Function Documentation

8.32.2.1 static int PhotonNetwork.AllocateSceneViewID () [static]

Enables the Master Client to allocate a viewID that is valid for scene objects.

Returns

A viewID that can be used for a new [PhotonView](#) or -1 in case of an error.

8.32.2.2 static int PhotonNetwork.AllocateViewID () [static]

Allocates a viewID that's valid for the current/local player.

Returns

A viewID that can be used for a new [PhotonView](#).

8.32.2.3 static void PhotonNetwork.CacheSendMessageTargets (Type type) [static]

Populates SendMessageTargets with currently existing GameObjects that have a Component of type.

Parameters

<i>type</i>	If null, this will use <code>SendMessageTargets</code> as component-type (MonoBehaviour by default).
-------------	--

8.32.2.4 static bool PhotonNetwork.CloseConnection (PhotonPlayer kickPlayer) [static]

Request a client to disconnect (KICK). Only the master client can do this

Only the target player gets this event. That player will disconnect automatically, which is what the others will notice, too.

Parameters

<i>kickPlayer</i>	The PhotonPlayer to kick.
-------------------	---

8.32.2.5 static bool PhotonNetwork.ConnectToBestCloudServer (string gameVersion) [static]

Connect to the [Photon](#) Cloud region with the lowest ping (on platforms that support Unity's Ping).

Will save the result of pinging all cloud servers in PlayerPrefs. Calling this the first time can take +-2 seconds. The ping result can be overridden via [PhotonNetwork.OverrideBestCloudServer\(..\)](#) This call can take up to 2 seconds if it is the first time you are using this, all cloud servers will be pinged to check for the best region.

The PUN Setup Wizard stores your appId in a settings file and applies a server address/port. To connect to the [Photon](#) Cloud, a valid AppId must be in the settings file (shown in the [Photon](#) Cloud Dashboard). <https://www.photonengine.com/dashboard>

Connecting to the [Photon](#) Cloud might fail due to:

- Invalid AppId (calls: [OnFailedToConnectToPhoton\(\)](#). check exact AppId value)
- Network issues (calls: [OnFailedToConnectToPhoton\(\)](#))
- Invalid region (calls: [OnConnectionFail\(\)](#) with `DisconnectCause.InvalidRegion`)
- Subscription CCU limit reached (calls: [OnConnectionFail\(\)](#) with `DisconnectCause.MaxCcuReached`. also calls: [OnPhotonMaxCcuReached\(\)](#))

More about the connection limitations: <http://doc.exitgames.com/en/pun>

Parameters

<i>gameVersion</i>	This client's version number. Users are separated from each other by gameversion (which allows you to make breaking changes).
--------------------	---

Returns

If this client is going to connect to cloud server based on ping. Even if true, this does not guarantee a connection but the attempt is being made.

8.32.2.6 static bool PhotonNetwork.ConnectToMaster (string masterServerAddress, int port, string appId, string gameVersion) [static]

Connect to a [Photon](#) Master Server by address, port, appId and game(client) version.

To connect to the [Photon](#) Cloud, a valid AppId must be in the settings file (shown in the [Photon](#) Cloud Dashboard). <https://www.photonengine.com/dashboard>

Connecting to the [Photon](#) Cloud might fail due to:

- Invalid AppId (calls: [OnFailedToConnectToPhoton\(\)](#). check exact AppId value)
- Network issues (calls: [OnFailedToConnectToPhoton\(\)](#))
- Invalid region (calls: [OnConnectionFail\(\)](#) with DisconnectCause.InvalidRegion)
- Subscription CCU limit reached (calls: [OnConnectionFail\(\)](#) with DisconnectCause.MaxCcuReached. also calls: [OnPhotonMaxCcuReached\(\)](#))

More about the connection limitations: <http://doc.exitgames.com/en/pun>

Parameters

<i>masterServer↔ Address</i>	The server's address (either your own or Photon Cloud address).
<i>port</i>	The server's port to connect to.
<i>appId</i>	Your application ID (Photon Cloud provides you with a GUID for your game).
<i>gameVersion</i>	This client's version number. Users are separated by gameversion (which allows you to make breaking changes).

8.32.2.7 static bool PhotonNetwork.ConnectToRegion ([CloudRegionCode](#) *region*, [string](#) *gameVersion*) [static]

Connects to the [Photon](#) Cloud region of choice.

8.32.2.8 static bool PhotonNetwork.ConnectUsingSettings ([string](#) *gameVersion*) [static]

Connect to [Photon](#) as configured in the editor (saved in PhotonServerSettings file).

This method will disable offlineMode (which won't destroy any instantiated GOs) and it will set isMessageQueue↔Running to true.

Your server configuration is created by the PUN Wizard and contains the AppId and region for [Photon](#) Cloud games and the server address if you host [Photon](#) yourself. These settings usually don't change often.

To ignore the config file and connect anywhere call: [PhotonNetwork.ConnectToMaster](#).

To connect to the [Photon](#) Cloud, a valid AppId must be in the settings file (shown in the [Photon](#) Cloud Dashboard). <https://www.photonengine.com/dashboard>

Connecting to the [Photon](#) Cloud might fail due to:

- Invalid AppId (calls: [OnFailedToConnectToPhoton\(\)](#). check exact AppId value)
- Network issues (calls: [OnFailedToConnectToPhoton\(\)](#))
- Invalid region (calls: [OnConnectionFail\(\)](#) with DisconnectCause.InvalidRegion)
- Subscription CCU limit reached (calls: [OnConnectionFail\(\)](#) with DisconnectCause.MaxCcuReached. also calls: [OnPhotonMaxCcuReached\(\)](#))

More about the connection limitations: <http://doc.exitgames.com/en/pun>

Parameters

<i>gameVersion</i>	This client's version number. Users are separated from each other by gameversion (which allows you to make breaking changes).
--------------------	---

8.32.2.9 static bool PhotonNetwork.CreateRoom ([string](#) *roomName*) [static]

Creates a room with given name but fails if this room(name) is existing already. Creates random name for room↔Name null.

If you don't want to create a unique room-name, pass null or "" as name and the server will assign a roomName (a GUID as string).

The created room is automatically placed in the currently used lobby (if any) or the default-lobby if you didn't explicitly join one.

Call this only on the master server. Internally, the master will respond with a server-address (and roomName, if needed). Both are used internally to switch to the assigned game server and roomName.

[PhotonNetwork.autoCleanUpPlayerObjects](#) will become this room's AutoCleanUp property and that's used by all clients that join this room.

Parameters

<i>roomName</i>	Unique name of the room to create.
-----------------	------------------------------------

Returns

If the operation got queued and will be sent.

8.32.2.10 `static bool PhotonNetwork.CreateRoom (string roomName, RoomOptions roomOptions, TypedLobby typedLobby) [static]`

Creates a room but fails if this room is existing already. Can only be called on Master Server.

When successful, this calls the callbacks OnCreatedRoom and OnJoinedRoom (the latter, cause you join as first player). If the room can't be created (because it exists already), OnPhotonCreateRoomFailed gets called.

If you don't want to create a unique room-name, pass null or "" as name and the server will assign a roomName (a GUID as string).

Rooms can be created in any number of lobbies. Those don't have to exist before you create a room in them (they get auto-created on demand). Lobbies can be useful to split room lists on the server-side already. That can help keep the room lists short and manageable. If you set a typedLobby parameter, the room will be created in that lobby (no matter if you are active in any). If you don't set a typedLobby, the room is automatically placed in the currently active lobby (if any) or the default-lobby.

Call this only on the master server. Internally, the master will respond with a server-address (and roomName, if needed). Both are used internally to switch to the assigned game server and roomName.

[PhotonNetwork.autoCleanUpPlayerObjects](#) will become this room's autoCleanUp property and that's used by all clients that join this room.

Parameters

<i>roomName</i>	Unique name of the room to create. Pass null or "" to make the server generate a name.
<i>roomOptions</i>	Common options for the room like MaxPlayers, initial custom room properties and similar. See RoomOptions type..
<i>typedLobby</i>	If null, the room is automatically created in the currently used lobby (which is "default" when you didn't join one explicitly).

Returns

If the operation got queued and will be sent.

8.32.2.11 `static bool PhotonNetwork.CreateRoom (string roomName, RoomOptions roomOptions, TypedLobby typedLobby, string[] expectedUsers) [static]`

Creates a room but fails if this room is existing already. Can only be called on Master Server.

When successful, this calls the callbacks OnCreatedRoom and OnJoinedRoom (the latter, cause you join as first player). If the room can't be created (because it exists already), OnPhotonCreateRoomFailed gets called.

If you don't want to create a unique room-name, pass null or "" as name and the server will assign a roomName (a GUID as string).

Rooms can be created in any number of lobbies. Those don't have to exist before you create a room in them (they get auto-created on demand). Lobbies can be useful to split room lists on the server-side already. That can help keep the room lists short and manageable. If you set a typedLobby parameter, the room will be created in that lobby (no matter if you are active in any). If you don't set a typedLobby, the room is automatically placed in the currently active lobby (if any) or the default-lobby.

Call this only on the master server. Internally, the master will respond with a server-address (and roomName, if needed). Both are used internally to switch to the assigned game server and roomName.

[PhotonNetwork.autoCleanUpPlayerObjects](#) will become this room's autoCleanUp property and that's used by all clients that join this room.

You can define an array of expectedUsers, to block player slots in the room for these users. The corresponding feature in [Photon](#) is called "Slot Reservation" and can be found in the doc pages.

Parameters

<i>roomName</i>	Unique name of the room to create. Pass null or "" to make the server generate a name.
<i>roomOptions</i>	Common options for the room like MaxPlayers, initial custom room properties and similar. See RoomOptions type..
<i>typedLobby</i>	If null, the room is automatically created in the currently used lobby (which is "default" when you didn't join one explicitly).
<i>expectedUsers</i>	Optional list of users (by UserId) who are expected to join this game and who you want to block a slot for.

Returns

If the operation got queued and will be sent.

8.32.2.12 static void PhotonNetwork.Destroy (PhotonView targetView) [static]

Network-Destroy the GameObject associated with the [PhotonView](#), unless the [PhotonView](#) is static or not under this client's control.

Destroying a networked GameObject while in a [Room](#) includes:

- Removal of the Instantiate call from the server's room buffer.
- Removing RPCs buffered for PhotonViews that got created indirectly with the [PhotonNetwork.Instantiate](#) call.
- Sending a message to other clients to remove the GameObject also (affected by network lag).

Usually, when you leave a room, the GOs get destroyed automatically. If you have to destroy a GO while not in a room, the Destroy is only done locally.

Destroying networked objects works only if they got created with [PhotonNetwork.Instantiate\(\)](#). Objects loaded with a scene are ignored, no matter if they have [PhotonView](#) components.

The GameObject must be under this client's control:

- Instantiated and owned by this client.
- Instantiated objects of players who left the room are controlled by the Master Client.
- Scene-owned game objects are controlled by the Master Client.
- GameObject can be destroyed while client is not in a room.

Returns

Nothing. Check error debug log for any issues.

8.32.2.13 static void PhotonNetwork.Destroy (GameObject *targetGo*) [static]

Network-Destroy the GameObject, unless it is static or not under this client's control.

Destroying a networked GameObject includes:

- Removal of the Instantiate call from the server's room buffer.
- Removing RPCs buffered for PhotonViews that got created indirectly with the [PhotonNetwork.Instantiate](#) call.
- Sending a message to other clients to remove the GameObject also (affected by network lag).

Usually, when you leave a room, the GOs get destroyed automatically. If you have to destroy a GO while not in a room, the Destroy is only done locally.

Destroying networked objects works only if they got created with [PhotonNetwork.Instantiate\(\)](#). Objects loaded with a scene are ignored, no matter if they have [PhotonView](#) components.

The GameObject must be under this client's control:

- Instantiated and owned by this client.
- Instantiated objects of players who left the room are controlled by the Master Client.
- Scene-owned game objects are controlled by the Master Client.
- GameObject can be destroyed while client is not in a room.

Returns

Nothing. Check error debug log for any issues.

8.32.2.14 static void PhotonNetwork.DestroyAll () [static]

Network-Destroy all GameObjects, PhotonViews and their RPCs in the room. Removes anything buffered from the server. Can only be called by Master Client (for anyone).

Can only be called by Master Client (for anyone). Unlike the Destroy methods, this will remove anything from the server's room buffer. If your game buffers anything beyond Instantiate and RPC calls, that will be cleaned as well from server.

Destroying all includes:

- Remove anything from the server's room buffer (Instantiate, RPCs, anything buffered).
- Sending a message to other clients to destroy everything locally, too (affected by network lag).

Destroying networked objects works only if they got created with [PhotonNetwork.Instantiate\(\)](#). Objects loaded with a scene are ignored, no matter if they have [PhotonView](#) components.

Returns

Nothing. Check error debug log for any issues.

8.32.2.15 static void PhotonNetwork.DestroyPlayerObjects (PhotonPlayer *targetPlayer*) [static]

Network-Destroy all GameObjects, PhotonViews and their RPCs of targetPlayer. Can only be called on local player (for "self") or Master Client (for anyone).

Destroying a networked GameObject includes:

- Removal of the Instantiate call from the server's room buffer.
- Removing RPCs buffered for PhotonViews that got created indirectly with the [PhotonNetwork.Instantiate](#) call.
- Sending a message to other clients to remove the GameObject also (affected by network lag).

Destroying networked objects works only if they got created with [PhotonNetwork.Instantiate\(\)](#). Objects loaded with a scene are ignored, no matter if they have [PhotonView](#) components.

Returns

Nothing. Check error debug log for any issues.

8.32.2.16 static void PhotonNetwork.DestroyPlayerObjects (int *targetPlayerId*) [static]

Network-Destroy all GameObjects, PhotonViews and their RPCs of this player (by ID). Can only be called on local player (for "self") or Master Client (for anyone).

Destroying a networked GameObject includes:

- Removal of the Instantiate call from the server's room buffer.
- Removing RPCs buffered for PhotonViews that got created indirectly with the [PhotonNetwork.Instantiate](#) call.
- Sending a message to other clients to remove the GameObject also (affected by network lag).

Destroying networked objects works only if they got created with [PhotonNetwork.Instantiate\(\)](#). Objects loaded with a scene are ignored, no matter if they have [PhotonView](#) components.

Returns

Nothing. Check error debug log for any issues.

8.32.2.17 static void PhotonNetwork.Disconnect () [static]

Makes this client disconnect from the photon server, a process that leaves any room and calls [OnDisconnectedFromPhoton](#) on completion.

When you disconnect, the client will send a "disconnecting" message to the server. This speeds up leave/disconnect messages for players in the same room as you (otherwise the server would timeout this client's connection). When used in `offlineMode`, the state-change and event-call [OnDisconnectedFromPhoton](#) are immediate. Offline mode is set to false as well. Once disconnected, the client can connect again. Use [ConnectUsingSettings](#).

8.32.2.18 delegate void PhotonNetwork.EventCallback (byte *eventCode*, object *content*, int *senderId*)

Defines the delegate usable in [OnEventCall](#).

Any `eventCode < 200` will be forwarded to your delegate(s).

Parameters

<i>eventCode</i>	The code assigned to the incoming event.
<i>content</i>	The content the sender put into the event.
<i>senderId</i>	The ID of the player who sent the event. It might be 0, if the "room" sent the event.

8.32.2.19 static void PhotonNetwork.FetchServerTimestamp () [static]

Refreshes the server timestamp (async operation, takes a roundtrip).

Can be useful if a bad connection made the timestamp unusable or imprecise.

8.32.2.20 static bool PhotonNetwork.FindFriends (string[] friendsToFind) [static]

Requests the rooms and online status for a list of friends and saves the result in [PhotonNetwork.Friends](#).

Works only on Master Server to find the rooms played by a selected list of users.

The result will be stored in [PhotonNetwork.Friends](#) when available. That list is initialized on first use of [OpFindFriends](#) (before that, it is null). To refresh the list, call FindFriends again (in 5 seconds or 10 or 20).

Users identify themselves by setting a unique userId in the [PhotonNetwork.AuthValues](#). See remarks of [AuthenticationValues](#) for info about how this is set and used.

The list of friends must be fetched from some other source (not provided by [Photon](#)).

Internal: The server response includes 2 arrays of info (each index matching a friend from the request): [ParameterCode.FindFriendsResponseOnlineList](#) = bool[] of online states [ParameterCode.FindFriendsResponseRoomIdList](#) = string[] of room names (empty string if not in a room)

Parameters

<i>friendsToFind</i>	Array of friend (make sure to use unique playerName or AuthValues).
----------------------	---

Returns

If the operation could be sent (requires connection, only one request is allowed at any time). Always false in offline mode.

8.32.2.21 static HashSet<GameObject> PhotonNetwork.FindGameObjectsWithComponent (Type type) [static]

Finds the GameObjects with Components of a specific type (using FindObjectsOfType).

Parameters

<i>type</i>	Type must be a Component
-------------	--------------------------

Returns

HashSet with GameObjects that have a specific type of Component.

8.32.2.22 static bool PhotonNetwork.GetCustomRoomList (TypedLobby typedLobby, string sqlLobbyFilter) [static]

Fetches a custom list of games from the server, matching a SQL-like "where" clause, then triggers [OnReceivedRoomListUpdate](#) callback.

Operation is only available for lobbies of type [SqlLobby](#). Note: You don't have to join that lobby. This is an async request.

When done, [OnReceivedRoomListUpdate](#) gets called. Use [GetRoomList\(\)](#) to access it.

http://doc.photonengine.com/en-us/pun/current/manuals-and-demos/matchmaking-and-lobby::sql_lobby_type

Parameters

<i>typedLobby</i>	The lobby to query. Has to be of type SqlLobby .
<i>sqlLobbyFilter</i>	The sql query statement.

Returns

If the operation could be sent (has to be connected).

8.32.2.23 static int PhotonNetwork.GetPing () [static]

The current roundtrip time to the photon server.

Returns

Roundtrip time (to server and back).

8.32.2.24 static RoomInfo [] PhotonNetwork.GetRoomList () [static]

Gets currently known rooms as [RoomInfo](#) array. This is available and updated while in a lobby (check `insideLobby`).

This list is a cached copy of the internal rooms list so it can be accessed each frame if needed. Per [RoomInfo](#) you can check if the room is full by comparing `playerCount` and `MaxPlayers` before you allow a join.

The name of a room must be used to join it (via `JoinRoom`).

Closed rooms are also listed by lobbies but they can't be joined. While in a room, any player can set [Room.visible](#) and [Room.open](#) to hide rooms from matchmaking and close them.

Returns

[RoomInfo](#)[] of current rooms in lobby.

8.32.2.25 static void PhotonNetwork.InitializeSecurity () [static]

Used for compatibility with Unity networking only. Encryption is automatically initialized while connecting.

8.32.2.26 static GameObject PhotonNetwork.Instantiate (string *prefabName*, Vector3 *position*, Quaternion *rotation*, int *group*) [static]

Instantiate a prefab over the network. This prefab needs to be located in the root of a "Resources" folder.

Instead of using prefabs in the Resources folder, you can manually Instantiate and assign PhotonViews. See doc.

Parameters

<i>prefabName</i>	Name of the prefab to instantiate.
<i>position</i>	Position Vector3 to apply on instantiation.
<i>rotation</i>	Rotation Quaternion to apply on instantiation.
<i>group</i>	The group for this PhotonView .

Returns

The new instance of a GameObject with initialized [PhotonView](#).

8.32.2.27 static GameObject PhotonNetwork.Instantiate (string *prefabName*, Vector3 *position*, Quaternion *rotation*, int *group*, object[] *data*) [static]

Instantiate a prefab over the network. This prefab needs to be located in the root of a "Resources" folder.

Instead of using prefabs in the Resources folder, you can manually Instantiate and assign PhotonViews. See doc.

Parameters

<i>prefabName</i>	Name of the prefab to instantiate.
<i>position</i>	Position Vector3 to apply on instantiation.
<i>rotation</i>	Rotation Quaternion to apply on instantiation.
<i>group</i>	The group for this PhotonView .
<i>data</i>	Optional instantiation data. This will be saved to it's PhotonView.instantiationData .

Returns

The new instance of a GameObject with initialized [PhotonView](#).

8.32.2.28 `static GameObject PhotonNetwork.InstantiateSceneObject (string prefabName, Vector3 position, Quaternion rotation, int group, object[] data) [static]`

Instantiate a scene-owned prefab over the network. The PhotonViews will be controllable by the MasterClient. This prefab needs to be located in the root of a "Resources" folder.

Only the master client can Instantiate scene objects. Instead of using prefabs in the Resources folder, you can manually Instantiate and assign PhotonViews. See doc.

Parameters

<i>prefabName</i>	Name of the prefab to instantiate.
<i>position</i>	Position Vector3 to apply on instantiation.
<i>rotation</i>	Rotation Quaternion to apply on instantiation.
<i>group</i>	The group for this PhotonView .
<i>data</i>	Optional instantiation data. This will be saved to it's PhotonView.instantiationData .

Returns

The new instance of a GameObject with initialized [PhotonView](#).

8.32.2.29 `static bool PhotonNetwork.JoinLobby () [static]`

On MasterServer this joins the default lobby which list rooms currently in use.

The room list is sent and refreshed by the server. You can access this cached list by [PhotonNetwork.GetRoomList\(\)](#).

Per room you should check if it's full or not before joining. [Photon](#) also lists rooms that are full, unless you close and hide them (room.open = false and room.visible = false).

In best case, you make your clients join random games, as described here: <http://doc.exitgames.com/en/realtime/current/reference/matchmaking-and-lobby>

You can show your current players and room count without joining a lobby (but you must be on the master server). Use: countOfPlayers, countOfPlayersOnMaster, countOfPlayersInRooms and countOfRooms.

You can use more than one lobby to keep the room lists shorter. See [JoinLobby\(TypedLobby lobby\)](#). When creating new rooms, they will be "attached" to the currently used lobby or the default lobby.

You can use JoinRandomRoom without being in a lobby! Set autoJoinLobby = false before you connect, to not join a lobby. In that case, the connect-workflow will call OnConnectedToMaster (if you implement it) when it's done.

8.32.2.30 `static bool PhotonNetwork.JoinLobby (TypedLobby typedLobby) [static]`

On a Master Server you can join a lobby to get lists of available rooms.

The room list is sent and refreshed by the server. You can access this cached list by [PhotonNetwork.GetRoomList\(\)](#).

Any client can "make up" any lobby on the fly. Splitting rooms into multiple lobbies will keep each list shorter. However, having too many lists might ruin the matchmaking experience.

In best case, you create a limited number of lobbies. For example, create a lobby per game-mode: "koth" for king of the hill and "ffa" for free for all, etc.

There is no listing of lobbies at the moment.

Sql-typed lobbies offer a different filtering model for random matchmaking. This might be more suited for skillbased-games. However, you will also need to follow the conventions for naming filterable properties in sql-lobbies! Both is explained in the matchmaking doc linked below.

In best case, you make your clients join random games, as described here: <http://confluence.exitgames.com/display/PTN/Op+JoinRandomGame>

Per room you should check if it's full or not before joining. Photon does list rooms that are full, unless you close and hide them (room.open = false and room.visible = false).

You can show your games current players and room count without joining a lobby (but you must be on the master server). Use: countOfPlayers, countOfPlayersOnMaster, countOfPlayersInRooms and countOfRooms.

When creating new rooms, they will be "attached" to the currently used lobby or the default lobby.

You can use JoinRandomRoom without being in a lobby! Set autoJoinLobby = false before you connect, to not join a lobby. In that case, the connect-workflow will call OnConnectedToMaster (if you implement it) when it's done.

Parameters

<i>typedLobby</i>	A typed lobby to join (must have name and type).
-------------------	--

8.32.2.31 `static bool PhotonNetwork.JoinOrCreateRoom (string roomName, RoomOptions roomOptions, TypedLobby typedLobby) [static]`

Lets you either join a named room or create it on the fly - you don't have to know if someone created the room already.

This makes it easier for groups of players to get into the same room. Once the group exchanged a roomName, any player can call JoinOrCreateRoom and it doesn't matter who actually joins or creates the room.

The parameters roomOptions and typedLobby are only used when the room actually gets created by this client. You know if this client created a room, if you get a callback OnCreatedRoom (before OnJoinedRoom gets called as well).

Parameters

<i>roomName</i>	Name of the room to join. Must be non null.
<i>roomOptions</i>	Options for the room, in case it does not exist yet. Else these values are ignored.
<i>typedLobby</i>	Lobby you want a new room to be listed in. Ignored if the room was existing and got joined.

Returns

If the operation got queued and will be sent.

8.32.2.32 `static bool PhotonNetwork.JoinOrCreateRoom (string roomName, RoomOptions roomOptions, TypedLobby typedLobby, string[] expectedUsers) [static]`

Lets you either join a named room or create it on the fly - you don't have to know if someone created the room already.

This makes it easier for groups of players to get into the same room. Once the group exchanged a roomName, any player can call JoinOrCreateRoom and it doesn't matter who actually joins or creates the room.

The parameters roomOptions and typedLobby are only used when the room actually gets created by this client. You know if this client created a room, if you get a callback OnCreatedRoom (before OnJoinedRoom gets called as

well).

You can define an array of `expectedUsers`, to block player slots in the room for these users. The corresponding feature in [Photon](#) is called "Slot Reservation" and can be found in the doc pages.

Parameters

<i>roomName</i>	Name of the room to join. Must be non null.
<i>roomOptions</i>	Options for the room, in case it does not exist yet. Else these values are ignored.
<i>typedLobby</i>	Lobby you want a new room to be listed in. Ignored if the room was existing and got joined.
<i>expectedUsers</i>	Optional list of users (by <code>UserId</code>) who are expected to join this game and who you want to block a slot for.

Returns

If the operation got queued and will be sent.

8.32.2.33 static bool PhotonNetwork.JoinRandomRoom () [static]

Joins any available room of the currently used lobby and fails if none is available.

Rooms can be created in arbitrary lobbies which get created on demand. You can join rooms from any lobby without actually joining the lobby. Use the `JoinRandomRoom` overload with [TypedLobby](#) parameter.

This method will only match rooms attached to one lobby! If you use many lobbies, you might have to repeat `JoinRandomRoom`, to find some fitting room. This method looks up a room in the currently active lobby or (if no lobby is joined) in the default lobby.

If this fails, you can still create a room (and make this available for the next who uses `JoinRandomRoom`). Alternatively, try again in a moment.

8.32.2.34 static bool PhotonNetwork.JoinRandomRoom (Hashtable expectedCustomRoomProperties, byte expectedMaxPlayers) [static]

Attempts to join an open room with fitting, custom properties but fails if none is currently available.

Rooms can be created in arbitrary lobbies which get created on demand. You can join rooms from any lobby without actually joining the lobby. Use the `JoinRandomRoom` overload with [TypedLobby](#) parameter.

This method will only match rooms attached to one lobby! If you use many lobbies, you might have to repeat `JoinRandomRoom`, to find some fitting room. This method looks up a room in the currently active lobby or (if no lobby is joined) in the default lobby.

If this fails, you can still create a room (and make this available for the next who uses `JoinRandomRoom`). Alternatively, try again in a moment.

Parameters

<i>expectedCustomRoomProperties</i>	Filters for rooms that match these custom properties (string keys and values). To ignore, pass null.
<i>expectedMaxPlayers</i>	Filters for a particular maxplayer setting. Use 0 to accept any maxPlayer value.

Returns

If the operation got queued and will be sent.

8.32.2.35 `static bool PhotonNetwork.JoinRandomRoom (Hashtable expectedCustomRoomProperties, byte expectedMaxPlayers, MatchmakingMode matchingType, TypedLobby typedLobby, string sqlLobbyFilter, string[] expectedUsers = null) [static]`

Attempts to join an open room with fitting, custom properties but fails if none is currently available.

Rooms can be created in arbitrary lobbies which get created on demand. You can join rooms from any lobby without actually joining the lobby with this overload.

This method will only match rooms attached to one lobby! If you use many lobbies, you might have to repeat `JoinRandomRoom`, to find some fitting room. This method looks up a room in the specified lobby or the currently active lobby (if none specified) or in the default lobby (if none active).

If this fails, you can still create a room (and make this available for the next who uses `JoinRandomRoom`). Alternatively, try again in a moment.

In `offlineMode`, a room will be created but no properties will be set and all parameters of this `JoinRandomRoom` call are ignored. The event/callback `OnJoinedRoom` gets called (see enum `PhotonNetworkingMessage`).

You can define an array of `expectedUsers`, to block player slots in the room for these users. The corresponding feature in [Photon](#) is called "Slot Reservation" and can be found in the doc pages.

Parameters

<i>expectedCustomRoomProperties</i>	Filters for rooms that match these custom properties (string keys and values). To ignore, pass null.
<i>expectedMaxPlayers</i>	Filters for a particular maxplayer setting. Use 0 to accept any maxPlayer value.
<i>matchingType</i>	Selects one of the available matchmaking algorithms. See <code>MatchmakingMode</code> enum for options.
<i>typedLobby</i>	The lobby in which you want to lookup a room. Pass null, to use the default lobby. This does not join that lobby and neither sets the lobby property.
<i>sqlLobbyFilter</i>	A filter-string for SQL-typed lobbies.
<i>expectedUsers</i>	Optional list of users (by <code>UserId</code>) who are expected to join this game and who you want to block a slot for.

Returns

If the operation got queued and will be sent.

8.32.2.36 `static bool PhotonNetwork.JoinRoom (string roomName) [static]`

Join room by roomname and on success calls `OnJoinedRoom()`. This is not affected by lobbies.

On success, the method `OnJoinedRoom()` is called on any script. You can implement it to react to joining a room.

`JoinRoom` fails if the room is either full or no longer available (it might become empty while you attempt to join). Implement `OnPhotonJoinRoomFailed()` to get a callback in error case.

To join a room from the lobby's listing, use `RoomInfo.Name` as `roomName` here. Despite using multiple lobbies, a `roomName` is always "global" for your application and so you don't have to specify which lobby it's in. The Master Server will find the room. In the [Photon](#) Cloud, an application is defined by `AppId`, `Game-` and `PUN-version`.

`PhotonNetworkingMessage.OnPhotonJoinRoomFailed` `PhotonNetworkingMessage.OnJoinedRoom`

Parameters

<i>roomName</i>	Unique name of the room to join.
-----------------	----------------------------------

Returns

If the operation got queued and will be sent.

8.32.2.37 `static bool PhotonNetwork.JoinRoom (string roomName, string[] expectedUsers) [static]`

Join room by roomname and on success calls [OnJoinedRoom\(\)](#). This is not affected by lobbies.

On success, the method [OnJoinedRoom\(\)](#) is called on any script. You can implement it to react to joining a room.

JoinRoom fails if the room is either full or no longer available (it might become empty while you attempt to join). Implement [OnPhotonJoinRoomFailed\(\)](#) to get a callback in error case.

To join a room from the lobby's listing, use [RoomInfo.Name](#) as roomName here. Despite using multiple lobbies, a roomName is always "global" for your application and so you don't have to specify which lobby it's in. The Master Server will find the room. In the [Photon](#) Cloud, an application is defined by AppId, Game- and PUN-version.

You can define an array of expectedUsers, to block player slots in the room for these users. The corresponding feature in [Photon](#) is called "Slot Reservation" and can be found in the doc pages.

PhotonNetworkingMessage.OnPhotonJoinRoomFailed PhotonNetworkingMessage.OnJoinedRoom

Parameters

<i>roomName</i>	Unique name of the room to join.
<i>expectedUsers</i>	Optional list of users (by UserId) who are expected to join this game and who you want to block a slot for.

Returns

If the operation got queued and will be sent.

8.32.2.38 `static bool PhotonNetwork.LeaveLobby () [static]`

Leave a lobby to stop getting updates about available rooms.

This does not reset [PhotonNetwork.lobby!](#) This allows you to join this particular lobby later easily.

The values countOfPlayers, countOfPlayersOnMaster, countOfPlayersInRooms and countOfRooms are received even without being in a lobby.

You can use JoinRandomRoom without being in a lobby. Use autoJoinLobby to not join a lobby when you connect.

8.32.2.39 `static bool PhotonNetwork.LeaveRoom () [static]`

Leave the current room and return to the Master Server where you can join or create rooms (see remarks).

This will clean up all (network) GameObjects with a [PhotonView](#), unless you changed autoCleanUp to false. Returns to the Master Server.

In OfflineMode, the local "fake" room gets cleaned up and OnLeftRoom gets called immediately.

8.32.2.40 `static void PhotonNetwork.LoadLevel (int levelNumber) [static]`

Wraps loading a level to pause the network message-queue. Optionally syncs the loaded level in a room.

To sync the loaded level in a room, set [PhotonNetwork.automaticallySyncScene](#) to true. The Master Client of a room will then sync the loaded level with every other player in the room.

While loading levels, it makes sense to not dispatch messages received by other players. This method takes care of that by setting [PhotonNetwork.isMessageQueueRunning](#) = false and enabling the queue when the level was loaded.

You should make sure you don't fire RPCs before you load another scene (which doesn't contain the same GameObjects and PhotonViews). You can call this in OnJoinedRoom.

This uses Application.LoadLevel.

Parameters

<i>levelNumber</i>	Number of the level to load. When using level numbers, make sure they are identical on all clients.
--------------------	---

8.32.2.41 static void PhotonNetwork.LoadLevel (string *levelName*) [static]

Wraps loading a level to pause the network message-queue. Optionally syncs the loaded level in a room.

While loading levels, it makes sense to not dispatch messages received by other players. This method takes care of that by setting [PhotonNetwork.isMessageQueueRunning](#) = false and enabling the queue when the level was loaded.

To sync the loaded level in a room, set [PhotonNetwork.automaticallySyncScene](#) to true. The Master Client of a room will then sync the loaded level with every other player in the room.

You should make sure you don't fire RPCs before you load another scene (which doesn't contain the same Game↔Objects and PhotonViews). You can call this in OnJoinedRoom.

This uses Application.LoadLevel.

Parameters

<i>levelName</i>	Name of the level to load. Make sure it's available to all clients in the same room.
------------------	--

8.32.2.42 static void PhotonNetwork.NetworkStatisticsReset () [static]

Resets the traffic stats and re-enables them.

8.32.2.43 static string PhotonNetwork.NetworkStatisticsToString () [static]

Only available when NetworkStatisticsEnabled was used to gather some stats.

Returns

A string with vital networking statistics.

8.32.2.44 static void PhotonNetwork.OverrideBestCloudServer (CloudRegionCode *region*) [static]

Overwrites the region that is used for [ConnectToBestCloudServer\(string gameVersion\)](#).

This will overwrite the result of pinging all cloud servers.

Use this to allow your users to save a manually selected region in the player preferences.

Note: You can also use [PhotonNetwork.ConnectToRegion](#) to (temporarily) connect to a specific region.

8.32.2.45 static bool PhotonNetwork.RaiseEvent (byte *eventCode*, object *eventContent*, bool *sendReliable*, RaiseEventOptions *options*) [static]

Sends fully customizable events in a room. Events consist of at least an [EventCode](#) (0..199) and can have content.

To receive the events someone sends, register your handling method in [PhotonNetwork.OnEventCall](#).

Example: private void OnEventHandler(byte eventCode, object content, int senderId) { Debug.Log("OnEvent↔Handler"); }

[PhotonNetwork.OnEventCall](#) += this.OnEventHandler;

With the senderId, you can look up the [PhotonPlayer](#) who sent the event. It is best practice to assign a eventCode for each different type of content and action. You have to cast the content.

The eventContent is optional. To be able to send something, it must be a "serializable type", something that the client can turn into a byte[] basically. Most basic types and arrays of them are supported, including Unity's Vector2, Vector3, Quaternion. Transforms or classes some project defines are NOT supported! You can make your own class a "serializable type" by following the example in [CustomTypes.cs](#).

The [RaiseEventOptions](#) have some (less intuitive) combination rules: If you set targetActors (an array of [Photon->Player.ID](#) values), the receivers parameter gets ignored. When using event caching, the targetActors, receivers and interestGroup can't be used. Buffered events go to all. When using cachingOption removeFromRoomCache, the eventCode and content are actually not sent but used as filter.

Parameters

<i>eventCode</i>	A byte identifying the type of event. You might want to use a code per action or to signal which content can be expected. Allowed: 0..199.
<i>eventContent</i>	Some serializable object like string, byte, integer, float (etc) and arrays of those. Hashtables with byte keys are good to send variable content.
<i>sendReliable</i>	Makes sure this event reaches all players. It gets acknowledged, which requires bandwidth and it can't be skipped (might add lag in case of loss).
<i>options</i>	Allows more complex usage of events. If null, RaiseEventOptions.Default will be used (which is fine).

Returns

False if event could not be sent

8.32.2.46 static bool PhotonNetwork.Reconnect () [static]

Can be used to reconnect to the master server after a disconnect.

After losing connection, you can use this to connect a client to the region Master Server again. Cache the room name you're in and use ReJoin(roomname) to return to a game. Common use case: Press the Lock Button on a iOS device and you get disconnected immediately.

8.32.2.47 static bool PhotonNetwork.ReconnectAndRejoin () [static]

When the client lost connection during gameplay, this method attempts to reconnect and rejoin the room.

This method re-connects directly to the game server which was hosting the room PUN was in before. If the room was shut down in the meantime, PUN will call OnPhotonJoinRoomFailed and return this client to the Master Server.

Check the return value, if this client will attempt a reconnect and rejoin (if the conditions are met). If Reconnect->AndRejoin returns false, you can still attempt a Reconnect and ReJoin.

Similar to PhotonNetwork.ReJoin, this requires you to use unique IDs per player (the UserID).

Returns

False, if there is no known room or game server to return to. Then, this client does not attempt the Reconnect->AndRejoin.

8.32.2.48 static void PhotonNetwork.RefreshCloudServerRating () [static]

Pings all cloud servers again to find the one with best ping (currently).

8.32.2.49 static bool PhotonNetwork.ReJoinRoom (string roomName) [static]

Can be used to return to a room after a disconnect and reconnect.

After losing connection, you might be able to return to a room and continue playing, if the client is reconnecting fast enough. Use [Reconnect\(\)](#) and this method. Cache the room name you're in and use `ReJoin(roomname)` to return to a game.

Note: To be able to ReJoin any room, you need to use UserIDs! You also need to set [RoomOptions.PlayerTtl](#).

Important: [Instantiate\(\)](#) and use of RPCs is not yet supported. The ownership rules of PhotonViews prevent a seamless return to a game. Use Custom Properties and RaiseEvent with event caching instead.

Common use case: Press the Lock Button on a iOS device and you get disconnected immediately.

8.32.2.50 `static void PhotonNetwork.RemovePlayerCustomProperties (string[] customPropertiesToDelete) [static]`

Locally removes Custom Properties of "this" player. Important: This does not synchronize the change! Useful when you switch rooms.

Use this method with care. It can create inconsistencies of state between players! This only changes the player's customProperties locally. This can be useful to clear your Custom Properties between games (let's say they store which turn you made, kills, etc).

[SetPlayerCustomProperties\(\)](#) syncs and can be used to set values to null while in a room. That can be considered "removed" while in a room.

If customPropertiesToDelete is null or has 0 entries, all Custom Properties are deleted (replaced with a new Hashtable). If you specify keys to remove, those will be removed from the Hashtable but other keys are unaffected.

Parameters

<i>customPropertiesToDelete</i>	List of Custom Property keys to remove. See remarks.
---------------------------------	--

8.32.2.51 `static void PhotonNetwork.RemoveRPCs (PhotonPlayer targetPlayer) [static]`

Remove all buffered RPCs from server that were sent by targetPlayer. Can only be called on local player (for "self") or Master Client (for anyone).

This method requires either:

- This is the targetPlayer's client.
- This client is the Master Client (can remove any [PhotonPlayer](#)'s RPCs).

If the targetPlayer calls RPCs at the same time that this is called, network lag will determine if those get buffered or cleared like the rest.

Parameters

<i>targetPlayer</i>	This player's buffered RPCs get removed from server buffer.
---------------------	---

8.32.2.52 `static void PhotonNetwork.RemoveRPCs (PhotonView targetPhotonView) [static]`

Remove all buffered RPCs from server that were sent via targetPhotonView. The Master Client and the owner of the targetPhotonView may call this.

This method requires either:

- The targetPhotonView is owned by this client (Instantiated by it).
- This client is the Master Client (can remove any [PhotonView](#)'s RPCs).

Parameters

<i>targetPhotonView</i>	RPCs buffered for this PhotonView get removed from server buffer.
-------------------------	---

8.32.2.53 static void PhotonNetwork.RemoveRPCsInGroup (int *targetGroup*) [static]

Remove all buffered RPCs from server that were sent in the *targetGroup*, if this is the Master Client or if this controls the individual [PhotonView](#).

This method requires either:

- This client is the Master Client (can remove any RPCs per group).
- Any other client: each [PhotonView](#) is checked if it is under this client's control. Only those RPCs are removed.

Parameters

<i>targetGroup</i>	Interest group that gets all RPCs removed.
--------------------	--

8.32.2.54 static void PhotonNetwork.SendOutgoingCommands () [static]

Can be used to immediately send the RPCs and Instantiates just called, so they are on their way to the other players.

This could be useful if you do a RPC to load a level and then load it yourself. While loading, no RPCs are sent to others, so this would delay the "load" RPC. You can send the RPC to "others", use this method, disable the message queue (by `isMessageQueueRunning`) and then load.

8.32.2.55 static void PhotonNetwork.SetInterestGroups (byte *group*, bool *enabled*) [static]

Enable/disable receiving events from a given Interest Group.

A client can tell the server which Interest Groups it's interested in. The server will only forward events for those Interest Groups to that client (saving bandwidth and performance).

See: <https://doc.photonengine.com/en-us/pun/current/manuals-and-demos/interestgroupsinterestgroups>

See: <https://doc.photonengine.com/en-us/pun/current/manuals-and-demos/culling-demo>

Parameters

<i>group</i>	The interest group to affect.
<i>enabled</i>	Sets if receiving from group to enabled (or not).

8.32.2.56 static void PhotonNetwork.SetInterestGroups (byte[] *disableGroups*, byte[] *enableGroups*) [static]

Enable/disable receiving on given Interest Groups (applied to PhotonViews).

A client can tell the server which Interest Groups it's interested in. The server will only forward events for those Interest Groups to that client (saving bandwidth and performance).

See: <https://doc.photonengine.com/en-us/pun/current/manuals-and-demos/interestgroupsinterestgroups>

See: <https://doc.photonengine.com/en-us/pun/current/manuals-and-demos/culling-demo>

Parameters

<i>disableGroups</i>	The interest groups to disable (or null).
<i>enableGroups</i>	The interest groups to enable (or null).

8.32.2.57 static void PhotonNetwork.SetLevelPrefix (short *prefix*) [static]

Sets level prefix for PhotonViews instantiated later on. Don't set it if you need only one!

Important: If you don't use multiple level prefixes, simply don't set this value. The default value is optimized out of the traffic.

This won't affect existing PhotonViews (they can't be changed yet for existing PhotonViews).

Messages sent with a different level prefix will be received but not executed. This affects RPCs, Instantiates and synchronization.

Be aware that PUN never resets this value, you'll have to do so yourself.

Parameters

<i>prefix</i>	Max value is short.MaxValue = 32767
---------------	-------------------------------------

8.32.2.58 static bool PhotonNetwork.SetMasterClient (PhotonPlayer *masterClientPlayer*) [static]

Asks the server to assign another player as Master Client of your current room.

RPCs and RaiseEvent have the option to send messages only to the Master Client of a room. SetMasterClient affects which client gets those messages.

This method calls an operation on the server to set a new Master Client, which takes a roundtrip. In case of success, this client and the others get the new Master Client from the server.

SetMasterClient tells the server which current Master Client should be replaced with the new one. It will fail, if anything switches the Master Client moments earlier. There is no callback for this error. All clients should get the new Master Client assigned by the server anyways.

See also: [PhotonNetwork.masterClient](#)

On v3 servers: The ReceiverGroup.MasterClient (usable in RPCs) is not affected by this (still points to lowest player.ID in room). Avoid using this enum value (and send to a specific player instead).

If the current Master Client leaves, PUN will detect a new one by "lowest player ID". Implement OnMasterClient↔ Switched to get a callback in this case. The PUN-selected Master Client might assign a new one.

Make sure you don't create an endless loop of Master-assigning! When selecting a custom Master Client, all clients should point to the same player, no matter who actually assigns this player.

Locally the Master Client is immediately switched, while remote clients get an event. This means the game is temporarily without Master Client like when a current Master Client leaves.

When switching the Master Client manually, keep in mind that this user might leave and not do it's work, just like any Master Client.

Parameters

<i>masterClient↔ Player</i>	The player to become the next Master Client.
---------------------------------	--

Returns

False when this operation couldn't be done. Must be in a room (not in offlineMode).

8.32.2.59 `static void PhotonNetwork.SetPlayerCustomProperties (Hashtable customProperties) [static]`

Sets this (local) player's properties and synchronizes them to the other players (don't modify them directly).

While in a room, your properties are synced with the other players. CreateRoom, JoinRoom and JoinRandomRoom will all apply your player's custom properties when you enter the room. The whole Hashtable will get sent. Minimize the traffic by setting only updated key/values.

If the Hashtable is null, the custom properties will be cleared. Custom properties are never cleared automatically, so they carry over to the next room, if you don't change them.

Don't set properties by modifying PhotonNetwork.player.customProperties!

Parameters

<i>customProperties</i>	Only string-typed keys will be used from this hashtable. If null, custom properties are all deleted.
-------------------------	--

8.32.2.60 `static void PhotonNetwork.SetReceivingEnabled (int group, bool enabled) [static]`

8.32.2.61 `static void PhotonNetwork.SetReceivingEnabled (int[] enableGroups, int[] disableGroups) [static]`

8.32.2.62 `static void PhotonNetwork.SetSendingEnabled (int group, bool enabled) [static]`

8.32.2.63 `static void PhotonNetwork.SetSendingEnabled (byte group, bool enabled) [static]`

Enable/disable sending on given group (applied to PhotonViews)

This does not interact with the [Photon](#) server-side. It's just a client-side setting to suppress updates, should they be sent to one of the blocked groups.

This setting is not particularly useful, as it means that updates literally never reach the server or anyone else. Use with care.

Parameters

<i>group</i>	The interest group to affect.
<i>enabled</i>	Sets if sending to group is enabled (or not).

8.32.2.64 `static void PhotonNetwork.SetSendingEnabled (int[] enableGroups, int[] disableGroups) [static]`

8.32.2.65 `static void PhotonNetwork.SetSendingEnabled (byte[] disableGroups, byte[] enableGroups) [static]`

Enable/disable sending on given groups (applied to PhotonViews)

This does not interact with the [Photon](#) server-side. It's just a client-side setting to suppress updates, should they be sent to one of the blocked groups.

This setting is not particularly useful, as it means that updates literally never reach the server or anyone else. Use with care.

Parameters

<i>enableGroups</i>	The interest groups to enable sending on (or null).
<i>disableGroups</i>	The interest groups to disable sending on (or null).

8.32.2.66 `static void PhotonNetwork.SwitchToProtocol (ConnectionProtocol cp) [static]`

While offline, the network protocol can be switched (which affects the ports you can use to connect).

When you switch the protocol, make sure to also switch the port for the master server. Default ports are: TCP: 4530
UDP: 5055

This could look like this:

```
Connect(serverAddress, <udpport|tcpport>, applID, gameVersion)
```

Or when you use [ConnectUsingSettings\(\)](#), the PORT in the settings can be switched like so:

```
PhotonNetwork.PhotonServerSettings.ServerPort = 4530;
```

The current protocol can be read this way:

```
PhotonNetwork.networkingPeer.UsedProtocol
```

This does not work with the native socket plugin of PUN+ on mobile!

Parameters

<i>cp</i>	Network protocol to use as low level connection. UDP is default. TCP is not available on all platforms (see remarks).
-----------	---

8.32.2.67 static void PhotonNetwork.UnAllocateViewID (int viewID) [static]

Unregister a viewID (of manually instantiated and destroyed networked objects).

Parameters

<i>viewID</i>	A viewID manually allocated by this player.
---------------	---

8.32.2.68 static bool PhotonNetwork.WebRpc (string name, object parameters) [static]

This operation makes [Photon](#) call your custom web-service by name (path) with the given parameters.

This is a server-side feature which must be setup in the [Photon](#) Cloud Dashboard prior to use.

See the Turnbased Feature Overview for a short intro.

<http://doc.photonengine.com/en/turnbased/current/getting-started/feature-overview>
br/> The Parameters will be converted into JSON format, so make sure your parameters are compatible.

See [PhotonNetworkingMessage.OnWebRpcResponse](#) on how to get a response.

It's important to understand that the [OperationResponse](#) only tells if the WebRPC could be called. The content of the response contains any values your web-service sent and the error/success code. In case the web-service failed, an error code and a debug message are usually inside the [OperationResponse](#).

The class [WebRpcResponse](#) is a helper-class that extracts the most valuable content from the WebRPC response.

Example callback implementation:

```
public void OnWebRpcResponse(OperationResponse response)
{
    WebRpcResponse webResponse = new WebRpcResponse(operationResponse);
    if (webResponse.ReturnCode != 0) { //...
    }

    switch (webResponse.Name) { //...
    }
    // and so on
}
```

8.32.3 Member Data Documentation

8.32.3.1 float PhotonNetwork.BackgroundTimeout = 60.0f [static]

Defines how many seconds PUN keeps the connection, after Unity's OnApplicationPause(true) call. Default: 60 seconds.

It's best practice to disconnect inactive apps/connections after a while but to also allow users to take calls, etc.. We think a reasonable background timeout is 60 seconds.

To handle the timeout, implement: [OnDisconnectedFromPhoton\(\)](#), as usual. Your application will "notice" the background disconnect when it becomes active again (running the Update() loop).

If you need to separate this case from others, you need to track if the app was in the background (there is no special callback by PUN).

A value below 0.1 seconds will disable this timeout (careful: connections can be kept indefinitely).

Info: PUN is running a "fallback thread" to send ACKs to the server, even when Unity is not calling Update() regularly. This helps keeping the connection while loading scenes and assets and when the app is in the background.

Note: Some platforms (e.g. iOS) don't allow to keep a connection while the app is in background. In those cases, this value does not change anything, the app immediately loses connection in background.

Unity's OnApplicationPause() callback is broken in some exports (Android) of some Unity versions. Make sure OnApplicationPause() gets the callbacks you'd expect on the platform you target! Check PhotonHandler.OnApplicationPause(bool pause), to see the implementation.

8.32.3.2 bool PhotonNetwork.InstantiateInRoomOnly = true [static]

If true, Instantiate methods will check if you are in a room and fail if you are not.

Instantiating anything outside of a specific room is very likely to break things. Turn this off only if you know what you do.

8.32.3.3 PhotonLogLevel PhotonNetwork.logLevel = PhotonLogLevel.ErrorsOnly [static]

Network log level. Controls how verbose PUN is.

8.32.3.4 readonly int PhotonNetwork.MAX_VIEW_IDS = 1000 [static]

The maximum number of assigned PhotonViews *per player* (or scene). See the [General Documentation](#) topic "Limitations" on how to raise this limitation.

8.32.3.5 int PhotonNetwork.maxConnections [static]

Only used in Unity Networking. In PUN, set the number of players in [PhotonNetwork.CreateRoom](#).

8.32.3.6 EventCallback PhotonNetwork.OnEventCall [static]

Register your RaiseEvent handling methods here by using "+=".

Any eventCode < 200 will be forwarded to your delegate(s).

[RaiseEvent](#)

8.32.3.7 ServerSettings PhotonNetwork.PhotonServerSettings = (ServerSettings)Resources.Load(PhotonNetwork.serverSettingsAssetFile, typeof(ServerSettings)) [static]

Serialized server settings, written by the Setup Wizard for use in ConnectUsingSettings.

8.32.3.8 `float PhotonNetwork.precisionForFloatSynchronization = 0.01f` [static]

The minimum difference between floats before we send it via a [PhotonView](#)'s OnSerialize/ObservingComponent.

8.32.3.9 `float PhotonNetwork.precisionForQuaternionSynchronization = 1.0f` [static]

The minimum angle that a rotation needs to change before we send it via a [PhotonView](#)'s OnSerialize/ObservingComponent.

8.32.3.10 `float PhotonNetwork.precisionForVectorSynchronization = 0.000099f` [static]

The minimum difference that a Vector2 or Vector3 (e.g. a transforms rotation) needs to change before we send it via a [PhotonView](#)'s OnSerialize/ObservingComponent.

Note that this is the sqrMagnitude. E.g. to send only after a 0.01 change on the Y-axis, we use $0.01f * 0.01f = 0.0001f$. As a remedy against float inaccuracy we use 0.000099f instead of 0.0001f.

8.32.3.11 `Dictionary<string, GameObject> PhotonNetwork.PrefabCache = new Dictionary<string, GameObject>()`
[static]

Keeps references to GameObjects for frequent instantiation (out of memory instead of loading the Resources).

You should be able to modify the cache anytime you like, except while Instantiate is used. Best do it only in the main-Thread.

8.32.3.12 `HashSet<GameObject> PhotonNetwork.SendMonoMessageTargets` [static]

If not null, this is the (exclusive) list of GameObjects that get called by PUN SendMonoMessage().

For all callbacks defined in PhotonNetworkingMessage, PUN will use SendMonoMessage and call FindObjectsOfType() to find all scripts and GameObjects that might want a callback by PUN.

PUN callbacks are not very frequent (in-game, property updates are most frequent) but FindObjectsOfType is time consuming and with a large number of GameObjects, performance might suffer.

Optionally, SendMonoMessageTargets can be used to supply a list of target GameObjects. This skips the FindObjectsOfType() but any GameObject that needs callbacks will have to Add itself to this list.

If null, the default behaviour is to do a SendMessage on each GameObject with a MonoBehaviour.

8.32.3.13 `Type PhotonNetwork.SendMonoMessageTargetType = typeof(MonoBehaviour)` [static]

Defines which classes can contain PUN Callback implementations.

This provides the option to optimize your runtime for speed.

The more specific this Type is, the fewer classes will be checked with reflection for callback methods.

8.32.3.14 `bool PhotonNetwork.StartRpcAsCoroutine = true` [static]

Can be used to skip starting RPCs as Coroutine, which can be a performance issue.

8.32.3.15 `bool PhotonNetwork.UsePrefabCache = true` [static]

While enabled (true), Instantiate uses [PhotonNetwork.PrefabCache](#) to keep game objects in memory (improving instantiation of the same prefab).

Setting `UsePrefabCache` to false during runtime will not clear `PrefabCache` but will ignore it right away. You could clean and modify the cache yourself. Read its comments.

8.32.3.16 `bool PhotonNetwork.UseRpcMonoBehaviourCache` [static]

While enabled, the `MonoBehaviours` on which we call RPCs are cached, avoiding costly `GetComponent<MonoBehaviour>()` calls.

RPCs are called on the `MonoBehaviours` of a target [PhotonView](#). Those have to be found via `GetComponent`.

When set this to true, the list of `MonoBehaviours` gets cached in each [PhotonView](#). You can use `PhotonView.RefreshRpcMonoBehaviourCache()` to manually refresh a [PhotonView](#)'s list of `MonoBehaviours` on demand (when a new `MonoBehaviour` gets added to a networked `GameObject`, e.g.).

8.32.3.17 `const string PhotonNetwork.versionPUN = "1.82"`

Version number of PUN. Also used in `GameVersion` to separate client version from each other.

8.32.4 Property Documentation

8.32.4.1 `AuthenticationValues PhotonNetwork.AuthValues` [static], [get], [set]

A user's authentication values used during connect.

Set these before calling `Connect` if you want custom authentication. These values set the `userId`, if and how that `userId` gets verified (server-side), etc..

If authentication fails for any values, PUN will call your implementation of `OnCustomAuthenticationFailed(string debugMsg)`. See: `PhotonNetworkingMessage.OnCustomAuthenticationFailed`

8.32.4.2 `bool PhotonNetwork.autoCleanUpPlayerObjects` [static], [get], [set]

This setting defines per room, if network-instantiated `GameObjects` (with [PhotonView](#)) get cleaned up when the creator of it leaves.

This setting is done per room. It can't be changed in the room and it will override the settings of individual clients.

If `room.AutoCleanUp` is enabled in a room, the PUN clients will destroy a player's `GameObjects` on leave. This includes `GameObjects` manually instantiated (via RPCs, e.g.). When enabled, the server will clean RPCs, instantiated `GameObjects` and `PhotonViews` of the leaving player, too. and Players who join after someone left, won't get the events of that player anymore.

Under the hood, this setting is stored as a Custom [Room](#) Property. Enabled by default.

8.32.4.3 `bool PhotonNetwork.autoJoinLobby` [static], [get], [set]

Set in `PhotonServerSettings` asset. Defines if the [PhotonNetwork](#) should join the "lobby" when connected to the Master server.

If this is false, `OnConnectedToMaster()` will be called when connection to the Master is available. `OnJoinedLobby()` will NOT be called if this is false.

Enabled by default.

The room listing will not become available. Rooms can be created and joined (randomly) without joining the lobby (and getting sent the room list).

8.32.4.4 `bool PhotonNetwork.automaticallySyncScene` `[static], [get], [set]`

Defines if all clients in a room should load the same level as the Master Client (if that used [PhotonNetwork.LoadScene\(\)](#)).

To synchronize the loaded level, the Master Client should use [PhotonNetwork.LoadLevel](#). All clients will load the new scene when they get the update or when they join.

Internally, a Custom [Room](#) Property is set for the loaded scene. When a client reads that and is not in the same scene yet, it will immediately pause the Message Queue ([PhotonNetwork.isMessageQueueRunning](#) = false) and load. When the scene finished loading, PUN will automatically re-enable the Message Queue.

8.32.4.5 `CloudRegionCode PhotonNetwork.CloudRegion` `[static], [get]`

Currently used Cloud [Region](#) (if any). As long as the client is not on a Master Server or Game Server, the region is not yet defined.

8.32.4.6 `bool PhotonNetwork.connected` `[static], [get]`

False until you connected to [Photon](#) initially. True in offline mode, while connected to any server and even while switching servers.

8.32.4.7 `bool PhotonNetwork.connectedAndReady` `[static], [get]`

A refined version of connected which is true only if your connection to the server is ready to accept operations like join, leave, etc.

8.32.4.8 `bool PhotonNetwork.connecting` `[static], [get]`

True when you called `ConnectUsingSettings` (or similar) until the low level connection to [Photon](#) gets established.

8.32.4.9 `ConnectionState PhotonNetwork.connectionState` `[static], [get]`

Simplified connection state

8.32.4.10 `ClientState PhotonNetwork.connectionStateDetailed` `[static], [get]`

Detailed connection state (ignorant of PUN, so it can be "disconnected" while switching servers).

In `OfflineMode`, this is `ClientState.Joined` (after create/join) or it is `ConnectedToMaster` in all other cases.

8.32.4.11 `int PhotonNetwork.countOfPlayers` `[static], [get]`

The count of players currently using this application (available on MasterServer in 5sec intervals).

8.32.4.12 `int PhotonNetwork.countOfPlayersInRooms` `[static], [get]`

Count of users currently playing your app in some room (sent every 5sec by Master Server). Use `playerList.Count` to get the count of players in the room you're in!

8.32.4.13 `int PhotonNetwork.countOfPlayersOnMaster` `[static], [get]`

The count of players currently looking for a room (available on MasterServer in 5sec intervals).

8.32.4.14 int PhotonNetwork.countOfRooms [static], [get]

The count of rooms currently in use (available on MasterServer in 5sec intervals).

While inside the lobby you can also check the count of listed rooms as: [PhotonNetwork.GetRoomList\(\).Length](#). Since PUN v1.25 this is only based on the statistic event [Photon](#) sends (counting all rooms).

8.32.4.15 bool PhotonNetwork.CrcCheckEnabled [static], [get], [set]

Crc checks can be useful to detect and avoid issues with broken datagrams. Can be enabled while not connected.

8.32.4.16 bool PhotonNetwork.EnableLobbyStatistics [static], [get], [set]

Set in PhotonServerSettings asset. Enable to get a list of active lobbies from the Master Server.

Lobby Statistics can be useful if a game uses multiple lobbies and you want to show activity of each to players.

This value is stored in PhotonServerSettings.

[PhotonNetwork.LobbyStatistics](#) is updated when you connect to the Master Server. There is also a callback [PunBehaviour](#).

8.32.4.17 List<FriendInfo> PhotonNetwork.Friends [static], [get], [set]

Read-only list of friends, their online status and the room they are in. Null until initialized by a FindFriends call.

Do not modify this list! It is internally handled by FindFriends and only available to read the values. The value of FriendListAge tells you how old the data is in milliseconds.

Don't get this list more often than useful (> 10 seconds). In best case, keep the list you fetch really short. You could (e.g.) get the full list only once, then request a few updates only for friends who are online. After a while (e.g. 1 minute), you can get the full list again (to update online states).

8.32.4.18 int PhotonNetwork.FriendsListAge [static], [get]

Age of friend list info (in milliseconds). It's 0 until a friend list is fetched.

8.32.4.19 string PhotonNetwork.gameVersion [static], [get], [set]

Version string for your this build. Can be used to separate incompatible clients. Sent during connect.

This is only sent when you connect so that is also the place you set it usually (e.g. in [ConnectUsingSettings](#)).

8.32.4.20 bool PhotonNetwork.inRoom [static], [get]

Is true while being in a room (connectionStateDetailed == ClientState.Joined).

Many actions can only be executed in a room, like Instantiate or Leave, etc. You can join a room in offline mode, too.

8.32.4.21 bool PhotonNetwork.insideLobby [static], [get]

True while this client is in a lobby.

Implement [IPunCallbacks.OnReceivedRoomListUpdate\(\)](#) for a notification when the list of rooms becomes available or updated.

You are automatically leaving any lobby when you join a room! Lobbies only exist on the Master Server (whereas rooms are handled by Game Servers).

8.32.4.22 `bool PhotonNetwork.isMasterClient` `[static], [get]`

Are we the master client?

8.32.4.23 `bool PhotonNetwork.isMessageQueueRunning` `[static], [get], [set]`

Can be used to pause dispatching of incoming events (RPCs, Instantiates and anything else incoming).

While `IsMessageQueueRunning == false`, the `OnPhotonSerializeView` calls are not done and nothing is sent by a client. Also, incoming messages will be queued until you re-activate the message queue.

This can be useful if you first want to load a level, then go on receiving data of `PhotonViews` and `RPCs`. The client will go on receiving and sending acknowledgements for incoming packages and your `RPCs/Events`. This adds "lag" and can cause issues when the pause is longer, as all incoming messages are just queued.

8.32.4.24 `bool PhotonNetwork.isNonMasterClientInRoom` `[static], [get]`

True if we are in a room (client) and NOT the room's masterclient

8.32.4.25 `TypedLobby PhotonNetwork.lobby` `[static], [get], [set]`

The lobby that will be used when PUN joins a lobby or creates a game.

The default lobby uses an empty string as name. PUN will enter a lobby on the Master Server if `autoJoinLobby` is set to true. So when you connect or leave a room, PUN automatically gets you into a lobby again.

Check [PhotonNetwork.insideLobby](#) if the client is in a lobby. ([Master Server And Lobby](#))

8.32.4.26 `List<TypedLobbyInfo> PhotonNetwork.LobbyStatistics` `[static], [get], [set]`

If turned on, the Master Server will provide information about active lobbies for this application.

Lobby Statistics can be useful if a game uses multiple lobbies and you want to show activity of each to players. Per lobby, you get: name, type, room- and player-count.

[PhotonNetwork.LobbyStatistics](#) is updated when you connect to the Master Server. There is also a callback `PunBehaviour.OnLobbyStatisticsUpdate`, which you should implement to update your UI (e.g.).

Lobby Statistics are not turned on by default. Enable them in the `PhotonServerSettings` file of the project.

8.32.4.27 `PhotonPlayer PhotonNetwork.masterClient` `[static], [get]`

The Master Client of the current room or null (outside of rooms).

Can be used as "authoritative" client/player to make decisions, run AI or other.

If the current Master Client leaves the room (leave/disconnect), the server will quickly assign someone else. If the current Master Client times out (closed app, lost connection, etc), messages sent to this client are effectively lost for the others! A timeout can take 10 seconds in which no Master Client is active.

Implement the method [IPunCallbacks.OnMasterClientSwitched](#) to be called when the Master Client switched.

Use [PhotonNetwork.SetMasterClient](#), to switch manually to some other player / client.

With `offlineMode == true`, this always returns the [PhotonNetwork.player](#).

8.32.4.28 `int PhotonNetwork.MaxResendsBeforeDisconnect` `[static], [get], [set]`

Defines the number of times a reliable message can be resent before not getting an ACK for it will trigger a disconnect. Default: 5.

Less resends mean quicker disconnects, while more can lead to much more lag without helping. Min: 3. Max: 10.

8.32.4.29 `bool PhotonNetwork.NetworkStatisticsEnabled` `[static], [get], [set]`

Enables or disables the collection of statistics about this client's traffic.

If you encounter issues with clients, the traffic stats are a good starting point to find solutions. Only with enabled stats, you can use `GetVitalStats`

8.32.4.30 `bool PhotonNetwork.offlineMode` `[static], [get], [set]`

Offline mode can be set to re-use your multiplayer code in singleplayer game modes. When this is on [PhotonNetwork](#) will not create any connections and there is near to no overhead. Mostly usefull for reusing RPC's and [PhotonNetwork.Instantiate](#)

8.32.4.31 `PhotonPlayer [] PhotonNetwork.otherPlayers` `[static], [get]`

The list of players in the current room, excluding the local player.

This list is only valid, while the client is in a room. It automatically gets updated when someone joins or leaves.

This can be used to list all other players in a room. Each player's [PhotonPlayer.customProperties](#) are accessible (set and synchronized via [PhotonPlayer.SetCustomProperties](#)).

You can use a [PhotonPlayer.TagObject](#) to store an arbitrary object for reference. That is not synchronized via the network.

8.32.4.32 `int PhotonNetwork.PacketLossByCrcCheck` `[static], [get]`

If `CrcCheckEnabled`, this counts the incoming packages that don't have a valid CRC checksum and got rejected.

8.32.4.33 `PhotonPlayer PhotonNetwork.player` `[static], [get]`

The local [PhotonPlayer](#). Always available and represents this player. `CustomProperties` can be set before entering a room and will be synced as well.

8.32.4.34 `PhotonPlayer [] PhotonNetwork.playerList` `[static], [get]`

The list of players in the current room, including the local player.

This list is only valid, while the client is in a room. It automatically gets updated when someone joins or leaves.

This can be used to list all players in a room. Each player's [PhotonPlayer.customProperties](#) are accessible (set and synchronized via [PhotonPlayer.SetCustomProperties](#)).

You can use a [PhotonPlayer.TagObject](#) to store an arbitrary object for reference. That is not synchronized via the network.

8.32.4.35 `string PhotonNetwork.playerName` `[static], [get], [set]`

Set to synchronize the player's nickname with everyone in the room(s) you enter. This sets [PhotonNetwork.player.NickName](#).

The playerName is just a nickname and does not have to be unique or backed up with some account. Set the value any time (e.g. before you connect) and it will be available to everyone you play with. Access the names of players by: [PhotonPlayer.NickName](#). [PhotonNetwork.otherPlayers](#) is a list of other players - each contains the playerName the remote player set.

8.32.4.36 **IPunPrefabPool** [PhotonNetwork.PrefabPool](#) [static], [get], [set]

An Object Pool can be used to keep and reuse instantiated object instances. It replaced Unity's default Instantiate and Destroy methods.

To use a GameObject pool, implement [IPunPrefabPool](#) and assign it here. Prefabs are identified by name.

8.32.4.37 **int** [PhotonNetwork.QuickResends](#) [static], [get], [set]

In case of network loss, reliable messages can be repeated quickly up to 3 times.

When reliable messages get lost more than once, subsequent repeats are delayed a bit to allow the network to recover.

With this option, the repeats 2 and 3 can be sped up. This can help avoid timeouts but also it increases the speed in which gaps are closed.

When you set this, increase [PhotonNetwork.MaxResendsBeforeDisconnect](#) to 6 or 7.

8.32.4.38 **int** [PhotonNetwork.ResentReliableCommands](#) [static], [get]

Count of commands that got repeated (due to local repeat-timing before an ACK was received).

If this value increases a lot, there is a good chance that a timeout disconnect will happen due to bad conditions.

8.32.4.39 **Room** [PhotonNetwork.room](#) [static], [get]

Get the room we're currently in. Null if we aren't in any room.

8.32.4.40 **int** [PhotonNetwork.sendRate](#) [static], [get], [set]

Defines how many times per second [PhotonNetwork](#) should send a package. If you change this, do not forget to also change 'sendRateOnSerialize'.

Less packages are less overhead but more delay. Setting the sendRate to 50 will create up to 50 packages per second (which is a lot!). Keep your target platform in mind: mobile networks are slower and less reliable.

8.32.4.41 **int** [PhotonNetwork.sendRateOnSerialize](#) [static], [get], [set]

Defines how many times per second OnPhotonSerialize should be called on PhotonViews.

Choose this value in relation to [PhotonNetwork.sendRate](#). OnPhotonSerialize will create updates and messages to be sent.

A lower rate takes up less performance but will cause more lag.

8.32.4.42 **ServerConnection** [PhotonNetwork.Server](#) [static], [get]

The server (type) this client is currently connected or connecting to.

[Photon](#) uses 3 different roles of servers: Name Server, Master Server and Game Server.

8.32.4.43 `string PhotonNetwork.ServerAddress` `[static], [get]`

Currently used server address (no matter if master or game server).

8.32.4.44 `int PhotonNetwork.ServerTimestamp` `[static], [get]`

The current server's millisecond timestamp.

This can be useful to sync actions and events on all clients in one room. The timestamp is based on the server's `Environment.TickCount`.

It will overflow from a positive to a negative value every so often, so be careful to use only time-differences to check the time delta when things happen.

This is the basis for [PhotonNetwork.time](#).

8.32.4.45 `double PhotonNetwork.time` `[static], [get]`

[Photon](#) network time, synched with the server.

v1.55

This time value depends on the server's `Environment.TickCount`. It is different per server but inside a [Room](#), all clients should have the same value (Rooms are on one server only).

This is not a `DateTime`!

Use this value with care:

It can start with any positive value.

It will "wrap around" from 4294967.295 to 0!

8.32.4.46 `int PhotonNetwork.unreliableCommandsLimit` `[static], [get], [set]`

Used once per dispatch to limit unreliable commands per channel (so after a pause, many channels can still cause a lot of unreliable commands)

8.33 PhotonPingManager Class Reference

Public Member Functions

- `IEnumerator` [PingSocket](#) ([Region](#) region)

Static Public Member Functions

- static `string` [ResolveHost](#) (`string` hostName)
Attempts to resolve a hostname into an IP string or returns empty string if that fails.

Public Attributes

- `bool` [UseNative](#)

Static Public Attributes

- static `int` [Attempts](#) = 5
- static `bool` [IgnoreInitialAttempt](#) = true
- static `int` [MaxMilliseconsPerPing](#) = 800

Properties

- [Region BestRegion](#) [get]
- bool [Done](#) [get]

8.33.1 Member Function Documentation

8.33.1.1 IEnumerator PhotonPingManager.PingSocket ([Region region](#))

Affected by frame-rate of app, as this Coroutine checks the socket for a result once per frame.

8.33.1.2 static string PhotonPingManager.ResolveHost (string *hostName*) [static]

Attempts to resolve a hostname into an IP string or returns empty string if that fails.

To be compatible with most platforms, the address family is checked like this: if (ipAddress.AddressFamily.ToString().Contains("6")) // ipv6... </remarks>

Parameters

<i>hostName</i>	Hostname to resolve.
-----------------	----------------------

Returns

IP string or empty string if resolution fails

8.33.2 Member Data Documentation

8.33.2.1 int PhotonPingManager.Attempts = 5 [static]

8.33.2.2 bool PhotonPingManager.IgnoreInitialAttempt = true [static]

8.33.2.3 int PhotonPingManager.MaxMillisecondsPerPing = 800 [static]

8.33.2.4 bool PhotonPingManager.UseNative

8.33.3 Property Documentation

8.33.3.1 [Region PhotonPingManager.BestRegion](#) [get]

8.33.3.2 bool PhotonPingManager.Done [get]

8.34 PhotonPlayer Class Reference

Summarizes a "player" within a room, identified (in that room) by actorID.

Inherits [IComparable< PhotonPlayer >](#), [IComparable< int >](#), [IEquatable< PhotonPlayer >](#), and [IEquatable< int >](#).

Public Member Functions

- [PhotonPlayer](#) (bool [isLocal](#), int actorID, string [name](#))
Creates a [PhotonPlayer](#) instance.
- override bool [Equals](#) (object p)
Makes [PhotonPlayer](#) comparable

- override int [GetHashCode](#) ()
- void [SetCustomProperties](#) ([Hashtable](#) propertiesToSet, [Hashtable](#) expectedValues=null, bool web↔Forward=false)
Updates the this player's Custom Properties with new/updated key-values.
- [PhotonPlayer](#) [Get](#) (int id)
- [PhotonPlayer](#) [GetNext](#) ()
- [PhotonPlayer](#) [GetNextFor](#) ([PhotonPlayer](#) currentPlayer)
- [PhotonPlayer](#) [GetNextFor](#) (int currentPlayerId)
- int [CompareTo](#) ([PhotonPlayer](#) other)
- int [CompareTo](#) (int other)
- bool [Equals](#) ([PhotonPlayer](#) other)
- bool [Equals](#) (int other)
- override string [ToString](#) ()
Brief summary string of the [PhotonPlayer](#). Includes name or player.ID and if it's the Master Client.
- string [ToStringFull](#) ()
String summary of the [PhotonPlayer](#): player.ID, name and all custom properties of this user.

Static Public Member Functions

- static [PhotonPlayer](#) [Find](#) (int ID)
Try to get a specific player by id.

Public Attributes

- readonly bool [IsLocal](#) = false
Only one player is controlled by each client. Others are not local.
- object [TagObject](#)
Can be used to store a reference that's useful to know "by player".

Properties

- int [ID](#) [get]
This player's actorID
- string [NickName](#) [get, set]
Nickname of this player.
- string [UserId](#) [get, set]
UserId of the player, available when the room got created with [RoomOptions.PublishUserId](#) = true.
- bool [IsMasterClient](#) [get]
True if this player is the Master Client of the current room.
- bool [IsInactive](#) [get, set]
Players might be inactive in a room when PlayerTTL for a room is > 0. If true, the player is not getting events from this room (now) but can return later.
- [Hashtable](#) [CustomProperties](#) [get, set]
Read-only cache for custom properties of player. Set via [PhotonPlayer.SetCustomProperties](#).
- [Hashtable](#) [AllProperties](#) [get]
Creates a Hashtable with all properties (custom and "well known" ones).
- string [name](#) [get, set]
- string [userId](#) [get, set]
- bool [isLocal](#) [get]
- bool [isMasterClient](#) [get]
- bool [isInactive](#) [get, set]
- [Hashtable](#) [customProperties](#) [get, set]
- [Hashtable](#) [allProperties](#) [get]

8.34.1 Detailed Description

Summarizes a "player" within a room, identified (in that room) by actorID.

Each player has an actorId (or ID), valid for that room. It's -1 until it's assigned by server. Each client can set it's player's custom properties with SetCustomProperties, even before being in a room. They are synced when joining a room.

8.34.2 Constructor & Destructor Documentation

8.34.2.1 PhotonPlayer.PhotonPlayer (bool *isLocal*, int *actorID*, string *name*)

Creates a [PhotonPlayer](#) instance.

Parameters

<i>isLocal</i>	If this is the local peer's player (or a remote one).
<i>actorID</i>	ID or ActorNumber of this player in the current room (a shortcut to identify each player in room)
<i>name</i>	Name of the player (a "well known property").

8.34.3 Member Function Documentation

8.34.3.1 int PhotonPlayer.CompareTo (PhotonPlayer *other*)

8.34.3.2 int PhotonPlayer.CompareTo (int *other*)

8.34.3.3 override bool PhotonPlayer.Equals (object *p*)

Makes [PhotonPlayer](#) comparable

8.34.3.4 bool PhotonPlayer.Equals (PhotonPlayer *other*)

8.34.3.5 bool PhotonPlayer.Equals (int *other*)

8.34.3.6 static PhotonPlayer PhotonPlayer.Find (int *ID*) [static]

Try to get a specific player by id.

Parameters

<i>ID</i>	ActorID
-----------	---------

Returns

The player with matching actorID or null, if the actorID is not in use.

8.34.3.7 PhotonPlayer PhotonPlayer.Get (int *id*)

8.34.3.8 override int PhotonPlayer.GetHashCode ()

8.34.3.9 PhotonPlayer PhotonPlayer.GetNext ()

8.34.3.10 PhotonPlayer PhotonPlayer.GetNextFor (PhotonPlayer *currentPlayer*)

8.34.3.11 PhotonPlayer PhotonPlayer.GetNextFor (int currentPlayerId)

8.34.3.12 void PhotonPlayer.SetCustomProperties (Hashtable propertiesToSet, Hashtable expectedValues = null, bool webForward = false)

Updates the this player's Custom Properties with new/updated key-values.

Custom Properties are a key-value set (Hashtable) which is available to all players in a room. They can relate to the room or individual players and are useful when only the current value of something is of interest. For example: The map of a room. All keys must be strings.

The [Room](#) and the [PhotonPlayer](#) class both have SetCustomProperties methods. Also, both classes offer access to current key-values by: customProperties.

Always use SetCustomProperties to change values. To reduce network traffic, set only values that actually changed. New properties are added, existing values are updated. Other values will not be changed, so only provide values that changed or are new.

To delete a named (custom) property of this room, use null as value.

Locally, SetCustomProperties will update it's cache without delay. Other clients are updated through [Photon](#) (the server) with a fitting operation.

Check and Swap

SetCustomProperties have the option to do a server-side Check-And-Swap (CAS): Values only get updated if the expected values are correct. The expectedValues can be different key/values than the propertiesToSet. So you can check some key and set another key's value (if the check succeeds).

If the client's knowledge of properties is wrong or outdated, it can't set values with CAS. This can be useful to keep players from concurrently setting values. For example: If all players try to pickup some card or item, only one should get it. With CAS, only the first SetProperty gets executed server-side and any other (sent at the same time) fails.

The server will broadcast successfully changed values and the local "cache" of customProperties only gets updated after a roundtrip (if anything changed).

You can do a "webForward": [Photon](#) will send the changed properties to a WebHook defined for your application.

OfflineMode

While [PhotonNetwork.offlineMode](#) is true, the expectedValues and webForward parameters are ignored. In OfflineMode, the local customProperties values are immediately updated (without the roundtrip).

Parameters

<i>propertiesToSet</i>	The new properties to be set.
<i>expectedValues</i>	At least one property key/value set to check server-side. Key and value must be correct. Ignored in OfflineMode.
<i>webForward</i>	Set to true, to forward the set properties to a WebHook, defined for this app (in Dashboard). Ignored in OfflineMode.

8.34.3.13 override string PhotonPlayer.ToString ()

Brief summary string of the [PhotonPlayer](#). Includes name or player.ID and if it's the Master Client.

8.34.3.14 string PhotonPlayer.ToStringFull ()

String summary of the [PhotonPlayer](#): player.ID, name and all custom properties of this user.

Use with care and not every frame! Converts the customProperties to a String on every single call.

8.34.4 Member Data Documentation

8.34.4.1 readonly bool PhotonPlayer.IsLocal = false

Only one player is controlled by each client. Others are not local.

8.34.4.2 object PhotonPlayer.TagObject

Can be used to store a reference that's useful to know "by player".

Example: Set a player's character as Tag by assigning the GameObject on Instantiate.

8.34.5 Property Documentation

8.34.5.1 Hashtable PhotonPlayer.AllProperties [get]

Creates a Hashtable with all properties (custom and "well known" ones).

If used more often, this should be cached.

8.34.5.2 Hashtable PhotonPlayer.allProperties [get]

8.34.5.3 Hashtable PhotonPlayer.CustomProperties [get], [set]

Read-only cache for custom properties of player. Set via [PhotonPlayer.SetCustomProperties](#).

Don't modify the content of this Hashtable. Use SetCustomProperties and the properties of this class to modify values. When you use those, the client will sync values with the server.

[SetCustomProperties](#)

8.34.5.4 Hashtable PhotonPlayer.customProperties [get], [set]

8.34.5.5 int PhotonPlayer.ID [get]

This player's actorID

8.34.5.6 bool PhotonPlayer.IsInactive [get], [set]

Players might be inactive in a room when PlayerTTL for a room is > 0 . If true, the player is not getting events from this room (now) but can return later.

8.34.5.7 bool PhotonPlayer.isInactive [get], [set]

8.34.5.8 bool PhotonPlayer.isLocal [get]

8.34.5.9 bool PhotonPlayer.IsMasterClient [get]

True if this player is the Master Client of the current room.

See also: [PhotonNetwork.masterClient](#).

8.34.5.10 bool PhotonPlayer.isMasterClient [get]

8.34.5.11 string PhotonPlayer.name [get], [set]

8.34.5.12 `string PhotonPlayer.NickName` `[get]`, `[set]`

Nickname of this player.

Set the [PhotonNetwork.playerName](#) to make the name synchronized in a room.

8.34.5.13 `string PhotonPlayer.UserId` `[get]`, `[set]`

UserId of the player, available when the room got created with [RoomOptions.PublishUserId](#) = true.

Useful for [PhotonNetwork.FindFriends](#) and blocking slots in a room for expected players (e.g. in [PhotonNetwork.CreateRoom](#)).

8.34.5.14 `string PhotonPlayer.userId` `[get]`, `[set]`

8.35 PhotonRigidbody2DView Class Reference

This class helps you to synchronize the velocities of a 2d physics RigidBody. Note that only the velocities are synchronized and because Unitys physics engine is not deterministic (ie. the results aren't always the same on all computers) - the actual positions of the objects may go out of sync. If you want to have the position of this object the same on all clients, you should also add a [PhotonTransformView](#) to synchronize the position. Simply add the component to your GameObject and make sure that the [PhotonRigidbody2DView](#) is added to the list of observed components

Inherits MonoBehaviour, and [IPunObservable](#).

Public Member Functions

- void [OnPhotonSerializeView](#) ([PhotonStream](#) stream, [PhotonMessageInfo](#) info)

Called by PUN several times per second, so that your script can write and read synchronization data for the [PhotonView](#).

8.35.1 Detailed Description

This class helps you to synchronize the velocities of a 2d physics RigidBody. Note that only the velocities are synchronized and because Unitys physics engine is not deterministic (ie. the results aren't always the same on all computers) - the actual positions of the objects may go out of sync. If you want to have the position of this object the same on all clients, you should also add a [PhotonTransformView](#) to synchronize the position. Simply add the component to your GameObject and make sure that the [PhotonRigidbody2DView](#) is added to the list of observed components

8.35.2 Member Function Documentation

8.35.2.1 `void PhotonRigidbody2DView.OnPhotonSerializeView (PhotonStream stream, PhotonMessageInfo info)`

Called by PUN several times per second, so that your script can write and read synchronization data for the [PhotonView](#).

This method will be called in scripts that are assigned as Observed component of a [PhotonView](#).

[PhotonNetwork.sendRateOnSerialize](#) affects how often this method is called.

[PhotonNetwork.sendRate](#) affects how often packages are sent by this client.

Implementing this method, you can customize which data a [PhotonView](#) regularly synchronizes. Your code defines what is being sent (content) and how your data is used by receiving clients.

Unlike other callbacks, *OnPhotonSerializeView* only gets called when it is assigned to a [PhotonView](#) as `PhotonView.observed` script.

To make use of this method, the [PhotonStream](#) is essential. It will be in "writing" mode on the client that controls a `PhotonView` (`PhotonStream.isWriting == true`) and in "reading mode" on the remote clients that just receive that the controlling client sends.

If you skip writing any value into the stream, PUN will skip the update. Used carefully, this can conserve bandwidth and messages (which have a limit per room/second).

Note that *OnPhotonSerializeView* is not called on remote clients when the sender does not send any update. This can't be used as "x-times per second Update()".

Implements [IPunObservable](#).

8.36 PhotonRigidbodyView Class Reference

This class helps you to synchronize the velocities of a physics `Rigidbody`. Note that only the velocities are synchronized and because Unity's physics engine is not deterministic (ie. the results aren't always the same on all computers) - the actual positions of the objects may go out of sync. If you want to have the position of this object the same on all clients, you should also add a [PhotonTransformView](#) to synchronize the position. Simply add the component to your `GameObject` and make sure that the [PhotonRigidbodyView](#) is added to the list of observed components

Inherits `MonoBehaviour`, and [IPunObservable](#).

Public Member Functions

- void [OnPhotonSerializeView](#) ([PhotonStream](#) stream, [PhotonMessageInfo](#) info)

Called by PUN several times per second, so that your script can write and read synchronization data for the [PhotonView](#).

8.36.1 Detailed Description

This class helps you to synchronize the velocities of a physics `Rigidbody`. Note that only the velocities are synchronized and because Unity's physics engine is not deterministic (ie. the results aren't always the same on all computers) - the actual positions of the objects may go out of sync. If you want to have the position of this object the same on all clients, you should also add a [PhotonTransformView](#) to synchronize the position. Simply add the component to your `GameObject` and make sure that the [PhotonRigidbodyView](#) is added to the list of observed components

8.36.2 Member Function Documentation

8.36.2.1 void PhotonRigidbodyView.OnPhotonSerializeView (PhotonStream stream, PhotonMessageInfo info)

Called by PUN several times per second, so that your script can write and read synchronization data for the [PhotonView](#).

This method will be called in scripts that are assigned as Observed component of a [PhotonView](#).

[PhotonNetwork.sendRateOnSerialize](#) affects how often this method is called.

[PhotonNetwork.sendRate](#) affects how often packages are sent by this client.

Implementing this method, you can customize which data a [PhotonView](#) regularly synchronizes. Your code defines what is being sent (content) and how your data is used by receiving clients.

Unlike other callbacks, *OnPhotonSerializeView* only gets called when it is assigned to a [PhotonView](#) as `PhotonView.observed` script.

To make use of this method, the [PhotonStream](#) is essential. It will be in "writing" mode" on the client that controls a PhotonView (PhotonStream.isWriting == true) and in "reading mode" on the remote clients that just receive that the controlling client sends.

If you skip writing any value into the stream, PUN will skip the update. Used carefully, this can conserve bandwidth and messages (which have a limit per room/second).

Note that OnPhotonSerializeView is not called on remote clients when the sender does not send any update. This can't be used as "x-times per second Update()".

Implements [IPunObservable](#).

8.37 PhotonStatsGui Class Reference

Basic GUI to show traffic and health statistics of the connection to [Photon](#), toggled by shift+tab.

Inherits MonoBehaviour.

Public Member Functions

- void [Start](#) ()
- void [Update](#) ()
Checks for shift+tab input combination (to toggle statsOn).
- void [OnGUI](#) ()
- void [TrafficStatsWindow](#) (int windowID)

Public Attributes

- bool [statsWindowOn](#) = true
Shows or hides GUI (does not affect if stats are collected).
- bool [statsOn](#) = true
Option to turn collecting stats on or off (used in [Update\(\)](#)).
- bool [healthStatsVisible](#)
Shows additional "health" values of connection.
- bool [trafficStatsOn](#)
Shows additional "lower level" traffic stats.
- bool [buttonsOn](#)
Show buttons to control stats and reset them.
- Rect [statsRect](#) = new Rect(0, 100, 200, 50)
Positioning rect for window.
- int [WindowId](#) = 100
Unity GUI Window ID (must be unique or will cause issues).

8.37.1 Detailed Description

Basic GUI to show traffic and health statistics of the connection to [Photon](#), toggled by shift+tab.

The shown health values can help identify problems with connection losses or performance. Example: If the time delta between two consecutive SendOutgoingCommands calls is a second or more, chances rise for a disconnect being caused by this (because acknowledgements to the server need to be sent in due time).

8.37.2 Member Function Documentation

8.37.2.1 void PhotonStatsGui.OnGUI ()

8.37.2.2 void PhotonStatsGui.Start ()

8.37.2.3 void PhotonStatsGui.TrafficStatsWindow (int *windowID*)

8.37.2.4 void PhotonStatsGui.Update ()

Checks for shift+tab input combination (to toggle statsOn).

8.37.3 Member Data Documentation

8.37.3.1 bool PhotonStatsGui.buttonsOn

Show buttons to control stats and reset them.

8.37.3.2 bool PhotonStatsGui.healthStatsVisible

Shows additional "health" values of connection.

8.37.3.3 bool PhotonStatsGui.statsOn = true

Option to turn collecting stats on or off (used in [Update\(\)](#)).

8.37.3.4 Rect PhotonStatsGui.statsRect = new Rect(0, 100, 200, 50)

Positioning rect for window.

8.37.3.5 bool PhotonStatsGui.statsWindowOn = true

Shows or hides GUI (does not affect if stats are collected).

8.37.3.6 bool PhotonStatsGui.trafficStatsOn

Shows additional "lower level" traffic stats.

8.37.3.7 int PhotonStatsGui.WindowId = 100

Unity GUI Window ID (must be unique or will cause issues).

8.38 PhotonStream Class Reference

This container is used in [OnPhotonSerializeView\(\)](#) to either provide incoming data of a [PhotonView](#) or for you to provide it.

Public Member Functions

- [PhotonStream](#) (bool write, object[] incomingData)
Creates a stream and initializes it. Used by PUN internally.
- void [SetReadStream](#) (object[] incomingData, byte pos=0)
- object [ReceiveNext](#) ()
Read next piece of data from the stream when isReading is true.
- object [PeekNext](#) ()
Read next piece of data from the stream without advancing the "current" item.
- void [SendNext](#) (object obj)
Add another piece of data to send it when isWriting is true.
- object[] [ToArray](#) ()
Turns the stream into a new object[].
- void [Serialize](#) (ref bool myBool)
Will read or write the value, depending on the stream's isWriting value.
- void [Serialize](#) (ref int myInt)
Will read or write the value, depending on the stream's isWriting value.
- void [Serialize](#) (ref string value)
Will read or write the value, depending on the stream's isWriting value.
- void [Serialize](#) (ref char value)
Will read or write the value, depending on the stream's isWriting value.
- void [Serialize](#) (ref short value)
Will read or write the value, depending on the stream's isWriting value.
- void [Serialize](#) (ref float obj)
Will read or write the value, depending on the stream's isWriting value.
- void [Serialize](#) (ref [PhotonPlayer](#) obj)
Will read or write the value, depending on the stream's isWriting value.
- void [Serialize](#) (ref [Vector3](#) obj)
Will read or write the value, depending on the stream's isWriting value.
- void [Serialize](#) (ref [Vector2](#) obj)
Will read or write the value, depending on the stream's isWriting value.
- void [Serialize](#) (ref [Quaternion](#) obj)
Will read or write the value, depending on the stream's isWriting value.

Properties

- bool [isWriting](#) [get]
If true, this client should add data to the stream to send it.
- bool [isReading](#) [get]
If true, this client should read data send by another client.
- int [Count](#) [get]
Count of items in the stream.

8.38.1 Detailed Description

This container is used in [OnPhotonSerializeView\(\)](#) to either provide incoming data of a [PhotonView](#) or for you to provide it.

The isWriting property will be true if this client is the "owner" of the [PhotonView](#) (and thus the GameObject). Add data to the stream and it's sent via the server to the other players in a room. On the receiving side, isWriting is false and the data should be read.

Send as few data as possible to keep connection quality up. An empty [PhotonStream](#) will not be sent.

Use either [Serialize\(\)](#) for reading and writing or [SendNext\(\)](#) and [ReceiveNext\(\)](#). The latter two are just explicit read and write methods but do about the same work as [Serialize\(\)](#). It's a matter of preference which methods you use.

See also

[PhotonNetworkingMessage](#)

8.38.2 Constructor & Destructor Documentation

8.38.2.1 [PhotonStream.PhotonStream \(bool write, object\[\] incomingData \)](#)

Creates a stream and initializes it. Used by PUN internally.

8.38.3 Member Function Documentation

8.38.3.1 [object PhotonStream.PeekNext \(\)](#)

Read next piece of data from the stream without advancing the "current" item.

8.38.3.2 [object PhotonStream.ReceiveNext \(\)](#)

Read next piece of data from the stream when `isReading` is true.

8.38.3.3 [void PhotonStream.SendNext \(object obj \)](#)

Add another piece of data to send it when `isWriting` is true.

8.38.3.4 [void PhotonStream.Serialize \(ref bool myBool \)](#)

Will read or write the value, depending on the stream's `isWriting` value.

8.38.3.5 [void PhotonStream.Serialize \(ref int myInt \)](#)

Will read or write the value, depending on the stream's `isWriting` value.

8.38.3.6 [void PhotonStream.Serialize \(ref string value \)](#)

Will read or write the value, depending on the stream's `isWriting` value.

8.38.3.7 [void PhotonStream.Serialize \(ref char value \)](#)

Will read or write the value, depending on the stream's `isWriting` value.

8.38.3.8 [void PhotonStream.Serialize \(ref short value \)](#)

Will read or write the value, depending on the stream's `isWriting` value.

8.38.3.9 [void PhotonStream.Serialize \(ref float obj \)](#)

Will read or write the value, depending on the stream's `isWriting` value.

8.38.3.10 void PhotonStream.Serialize (ref PhotonPlayer *obj*)

Will read or write the value, depending on the stream's isWriting value.

8.38.3.11 void PhotonStream.Serialize (ref Vector3 *obj*)

Will read or write the value, depending on the stream's isWriting value.

8.38.3.12 void PhotonStream.Serialize (ref Vector2 *obj*)

Will read or write the value, depending on the stream's isWriting value.

8.38.3.13 void PhotonStream.Serialize (ref Quaternion *obj*)

Will read or write the value, depending on the stream's isWriting value.

8.38.3.14 void PhotonStream.SetReadStream (object[] *incomingData*, byte *pos* = 0)

8.38.3.15 object [] PhotonStream.ToArray ()

Turns the stream into a new object[].

8.38.4 Property Documentation

8.38.4.1 int PhotonStream.Count [get]

Count of items in the stream.

8.38.4.2 bool PhotonStream.isReading [get]

If true, this client should read data send by another client.

8.38.4.3 bool PhotonStream.isWriting [get]

If true, this client should add data to the stream to send it.

8.39 PhotonStreamQueue Class Reference

The [PhotonStreamQueue](#) helps you poll object states at higher frequencies then what [PhotonNetwork.sendRate](#) dictates and then sends all those states at once when [Serialize\(\)](#) is called. On the receiving end you can call [Deserialize\(\)](#) and then the stream will roll out the received object states in the same order and timeStep they were recorded in.

Public Member Functions

- [PhotonStreamQueue](#) (int sampleRate)
Initializes a new instance of the PhotonStreamQueue class.
- void [Reset](#) ()
Resets the PhotonStreamQueue. You need to do this whenever the amount of objects you are observing changes

- void [SendNext](#) (object obj)
Adds the next object to the queue. This works just like [PhotonStream.SendNext](#)
- bool [HasQueuedObjects](#) ()
Determines whether the queue has stored any objects
- object [ReceiveNext](#) ()
Receives the next object from the queue. This works just like [PhotonStream.ReceiveNext](#)
- void [Serialize](#) ([PhotonStream](#) stream)
Serializes the specified stream. Call this in your OnPhotonSerializeView method to send the whole recorded stream.
- void [Deserialize](#) ([PhotonStream](#) stream)
Deserializes the specified stream. Call this in your OnPhotonSerializeView method to receive the whole recorded stream.

8.39.1 Detailed Description

The [PhotonStreamQueue](#) helps you poll object states at higher frequencies then what [PhotonNetwork.sendRate](#) dictates and then sends all those states at once when [Serialize\(\)](#) is called. On the receiving end you can call [Deserialize\(\)](#) and then the stream will roll out the received object states in the same order and timeStep they were recorded in.

8.39.2 Constructor & Destructor Documentation

8.39.2.1 PhotonStreamQueue.PhotonStreamQueue (int *sampleRate*)

Initializes a new instance of the [PhotonStreamQueue](#) class.

Parameters

<i>sampleRate</i>	How many times per second should the object states be sampled
-------------------	---

8.39.3 Member Function Documentation

8.39.3.1 void PhotonStreamQueue.Deserialize ([PhotonStream](#) stream)

Deserializes the specified stream. Call this in your OnPhotonSerializeView method to receive the whole recorded stream.

Parameters

<i>stream</i>	The PhotonStream you receive as a parameter in OnPhotonSerializeView
---------------	--

8.39.3.2 bool PhotonStreamQueue.HasQueuedObjects ()

Determines whether the queue has stored any objects

8.39.3.3 object PhotonStreamQueue.ReceiveNext ()

Receives the next object from the queue. This works just like [PhotonStream.ReceiveNext](#)

Returns

8.39.3.4 void PhotonStreamQueue.Reset ()

Resets the [PhotonStreamQueue](#). You need to do this whenever the amount of objects you are observing changes

8.39.3.5 void PhotonStreamQueue.SendNext (object *obj*)

Adds the next object to the queue. This works just like [PhotonStream.SendNext](#)

Parameters

<i>obj</i>	The object you want to add to the queue
------------	---

8.39.3.6 void PhotonStreamQueue.Serialize (PhotonStream *stream*)

Serializes the specified stream. Call this in your OnPhotonSerializeView method to send the whole recorded stream.

Parameters

<i>stream</i>	The PhotonStream you receive as a parameter in OnPhotonSerializeView
---------------	--

8.40 PhotonTransformView Class Reference

This class helps you to synchronize position, rotation and scale of a GameObject. It also gives you many different options to make the synchronized values appear smooth, even when the data is only send a couple of times per second. Simply add the component to your GameObject and make sure that the [PhotonTransformView](#) is added to the list of observed components

Inherits MonoBehaviour, and [IPunObservable](#).

Public Member Functions

- void [SetSynchronizedValues](#) (Vector3 speed, float turnSpeed)
These values are synchronized to the remote objects if the interpolation mode or the extrapolation mode SynchronizeValues is used. Your movement script should pass on the current speed (in units/second) and turning speed (in angles/second) so the remote object can use them to predict the objects movement.
- void [OnPhotonSerializeView](#) (PhotonStream stream, PhotonMessageInfo info)
Called by PUN several times per second, so that your script can write and read synchronization data for the [Photon↔View](#).

8.40.1 Detailed Description

This class helps you to synchronize position, rotation and scale of a GameObject. It also gives you many different options to make the synchronized values appear smooth, even when the data is only send a couple of times per second. Simply add the component to your GameObject and make sure that the [PhotonTransformView](#) is added to the list of observed components

8.40.2 Member Function Documentation

8.40.2.1 void PhotonTransformView.OnPhotonSerializeView (PhotonStream *stream*, PhotonMessageInfo *info*)

Called by PUN several times per second, so that your script can write and read synchronization data for the [Photon↔View](#).

This method will be called in scripts that are assigned as Observed component of a [PhotonView](#).

[PhotonNetwork.sendRateOnSerialize](#) affects how often this method is called.

[PhotonNetwork.sendRate](#) affects how often packages are sent by this client.

Implementing this method, you can customize which data a [PhotonView](#) regularly synchronizes. Your code defines what is being sent (content) and how your data is used by receiving clients.

Unlike other callbacks, *OnPhotonSerializeView only gets called when it is assigned to a [PhotonView](#) as PhotonView.observed script.*

To make use of this method, the [PhotonStream](#) is essential. It will be in "writing" mode" on the client that controls a PhotonView (PhotonStream.isWriting == true) and in "reading mode" on the remote clients that just receive that the controlling client sends.

If you skip writing any value into the stream, PUN will skip the update. Used carefully, this can conserve bandwidth and messages (which have a limit per room/second).

Note that OnPhotonSerializeView is not called on remote clients when the sender does not send any update. This can't be used as "x-times per second Update()".

Implements [IPunObservable](#).

8.40.2.2 void PhotonTransformView.SetSynchronizedValues (Vector3 speed, float turnSpeed)

These values are synchronized to the remote objects if the interpolation mode or the extrapolation mode SynchronizeValues is used. Your movement script should pass on the current speed (in units/second) and turning speed (in angles/second) so the remote object can use them to predict the objects movement.

Parameters

<i>speed</i>	The current movement vector of the object in units/second.
<i>turnSpeed</i>	The current turn speed of the object in angles/second.

8.41 PhotonTransformViewPositionControl Class Reference

Public Member Functions

- [PhotonTransformViewPositionControl](#) ([PhotonTransformViewPositionModel](#) model)
- void [SetSynchronizedValues](#) (Vector3 speed, float turnSpeed)

These values are synchronized to the remote objects if the interpolation mode or the extrapolation mode SynchronizeValues is used. Your movement script should pass on the current speed (in units/second) and turning speed (in angles/second) so the remote object can use them to predict the objects movement.
- Vector3 [UpdatePosition](#) (Vector3 currentPosition)

Calculates the new position based on the values setup in the inspector
- Vector3 [GetNetworkPosition](#) ()

Gets the last position that was received through the network
- Vector3 [GetExtrapolatedPositionOffset](#) ()

Calculates an estimated position based on the last synchronized position, the time when the last position was received and the movement speed of the object
- void [OnPhotonSerializeView](#) (Vector3 currentPosition, [PhotonStream](#) stream, [PhotonMessageInfo](#) info)

8.41.1 Constructor & Destructor Documentation

8.41.1.1 PhotonTransformViewPositionControl.PhotonTransformViewPositionControl ([PhotonTransformViewPositionModel](#) model)

8.41.2 Member Function Documentation

8.41.2.1 Vector3 PhotonTransformViewPositionControl.GetExtrapolatedPositionOffset ()

Calculates an estimated position based on the last synchronized position, the time when the last position was received and the movement speed of the object

Returns

Estimated position of the remote object

8.41.2.2 Vector3 PhotonTransformViewPositionControl.GetNetworkPosition ()

Gets the last position that was received through the network

Returns

8.41.2.3 void PhotonTransformViewPositionControl.OnPhotonSerializeView (Vector3 *currentPosition*, PhotonStream *stream*, PhotonMessageInfo *info*)

8.41.2.4 void PhotonTransformViewPositionControl.SetSynchronizedValues (Vector3 *speed*, float *turnSpeed*)

These values are synchronized to the remote objects if the interpolation mode or the extrapolation mode SynchronizeValues is used. Your movement script should pass on the current speed (in units/second) and turning speed (in angles/second) so the remote object can use them to predict the objects movement.

Parameters

<i>speed</i>	The current movement vector of the object in units/second.
<i>turnSpeed</i>	The current turn speed of the object in angles/second.

8.41.2.5 Vector3 PhotonTransformViewPositionControl.UpdatePosition (Vector3 *currentPosition*)

Calculates the new position based on the values setup in the inspector

Parameters

<i>currentPosition</i>	The current position.
------------------------	-----------------------

Returns

The new position.

8.42 PhotonTransformViewPositionModel Class Reference

Public Types

- enum [InterpolateOptions](#) { [InterpolateOptions.Disabled](#), [InterpolateOptions.FixedSpeed](#), [InterpolateOptions.EstimatedSpeed](#), [InterpolateOptions.SynchronizeValues](#), [InterpolateOptions.Lerp](#) }
- enum [ExtrapolateOptions](#) { [ExtrapolateOptions.Disabled](#), [ExtrapolateOptions.SynchronizeValues](#), [ExtrapolateOptions.EstimateSpeedAndTurn](#), [ExtrapolateOptions.FixedSpeed](#) }

Public Attributes

- bool [SynchronizeEnabled](#)
- bool [TeleportEnabled](#) = true
- float [TeleportIfDistanceGreaterThan](#) = 3f
- [InterpolateOptions](#) [InterpolateOption](#) = InterpolateOptions.EstimatedSpeed
- float [InterpolateMoveTowardsSpeed](#) = 1f
- float [InterpolateLerpSpeed](#) = 1f
- float [InterpolateMoveTowardsAcceleration](#) = 2
- float [InterpolateMoveTowardsDeceleration](#) = 2
- AnimationCurve [InterpolateSpeedCurve](#)
- [ExtrapolateOptions](#) [ExtrapolateOption](#) = ExtrapolateOptions.Disabled
- float [ExtrapolateSpeed](#) = 1f
- bool [ExtrapolateIncludingRoundTripTime](#) = true
- int [ExtrapolateNumberOfStoredPositions](#) = 1
- bool [DrawErrorGizmo](#) = true

8.42.1 Member Enumeration Documentation

8.42.1.1 enum PhotonTransformViewPositionModel.ExtrapolateOptions

Enumerator

Disabled
SynchronizeValues
EstimateSpeedAndTurn
FixedSpeed

8.42.1.2 enum PhotonTransformViewPositionModel.InterpolateOptions

Enumerator

Disabled
FixedSpeed
EstimatedSpeed
SynchronizeValues
Lerp

8.42.2 Member Data Documentation

- 8.42.2.1 bool PhotonTransformViewPositionModel.DrawErrorGizmo = true
- 8.42.2.2 bool PhotonTransformViewPositionModel.ExtrapolateIncludingRoundTripTime = true
- 8.42.2.3 int PhotonTransformViewPositionModel.ExtrapolateNumberOfStoredPositions = 1
- 8.42.2.4 [ExtrapolateOptions](#) PhotonTransformViewPositionModel.ExtrapolateOption = ExtrapolateOptions.Disabled
- 8.42.2.5 float PhotonTransformViewPositionModel.ExtrapolateSpeed = 1f
- 8.42.2.6 float PhotonTransformViewPositionModel.InterpolateLerpSpeed = 1f

8.42.2.7 float PhotonTransformViewPositionModel.InterpolateMoveTowardsAcceleration = 2

8.42.2.8 float PhotonTransformViewPositionModel.InterpolateMoveTowardsDeceleration = 2

8.42.2.9 float PhotonTransformViewPositionModel.InterpolateMoveTowardsSpeed = 1f

8.42.2.10 InterpolateOptions PhotonTransformViewPositionModel.InterpolateOption = InterpolateOptions.EstimatedSpeed

8.42.2.11 AnimationCurve PhotonTransformViewPositionModel.InterpolateSpeedCurve

Initial value:

```
= new AnimationCurve( new Keyframe[] {
    new Keyframe( -1, 0, 0, Mathf
        .Infinity ),
    new Keyframe( 0, 1, 0, 0 ),
    new Keyframe( 1, 1, 0, 1 ),
    new Keyframe( 4, 4, 1, 0 ) }
)
```

8.42.2.12 bool PhotonTransformViewPositionModel.SynchronizeEnabled

8.42.2.13 bool PhotonTransformViewPositionModel.TeleportEnabled = true

8.42.2.14 float PhotonTransformViewPositionModel.TeleportIfDistanceGreaterThan = 3f

8.43 PhotonTransformViewRotationControl Class Reference

Public Member Functions

- [PhotonTransformViewRotationControl](#) ([PhotonTransformViewRotationModel](#) model)
- Quaternion [GetNetworkRotation](#) ()
Gets the last rotation that was received through the network
- Quaternion [GetRotation](#) (Quaternion currentRotation)
- void [OnPhotonSerializeView](#) (Quaternion currentRotation, [PhotonStream](#) stream, [PhotonMessageInfo](#) info)

8.43.1 Constructor & Destructor Documentation

8.43.1.1 PhotonTransformViewRotationControl.PhotonTransformViewRotationControl ([PhotonTransformViewRotationModel](#) model)

8.43.2 Member Function Documentation

8.43.2.1 Quaternion PhotonTransformViewRotationControl.GetNetworkRotation ()

Gets the last rotation that was received through the network

Returns

8.43.2.2 Quaternion PhotonTransformViewRotationControl.GetRotation (Quaternion *currentRotation*)

8.43.2.3 void PhotonTransformViewRotationControl.OnPhotonSerializeView (Quaternion *currentRotation*, PhotonStream *stream*, PhotonMessageInfo *info*)

8.44 PhotonTransformViewRotationModel Class Reference

Public Types

- enum [InterpolateOptions](#) { [InterpolateOptions.Disabled](#), [InterpolateOptions.RotateTowards](#), [InterpolateOptions.Lerp](#) }

Public Attributes

- bool [SynchronizeEnabled](#)
- [InterpolateOptions](#) [InterpolateOption](#) = [InterpolateOptions.RotateTowards](#)
- float [InterpolateRotateTowardsSpeed](#) = 180
- float [InterpolateLerpSpeed](#) = 5

8.44.1 Member Enumeration Documentation

8.44.1.1 enum PhotonTransformViewRotationModel.InterpolateOptions

Enumerator

Disabled

RotateTowards

Lerp

8.44.2 Member Data Documentation

8.44.2.1 float PhotonTransformViewRotationModel.InterpolateLerpSpeed = 5

8.44.2.2 [InterpolateOptions](#) PhotonTransformViewRotationModel.InterpolateOption = [InterpolateOptions.RotateTowards](#)

8.44.2.3 float PhotonTransformViewRotationModel.InterpolateRotateTowardsSpeed = 180

8.44.2.4 bool PhotonTransformViewRotationModel.SynchronizeEnabled

8.45 PhotonTransformViewScaleControl Class Reference

Public Member Functions

- [PhotonTransformViewScaleControl](#) ([PhotonTransformViewScaleModel](#) model)
- Vector3 [GetNetworkScale](#) ()
Gets the last scale that was received through the network
- Vector3 [GetScale](#) (Vector3 currentScale)
- void [OnPhotonSerializeView](#) (Vector3 currentScale, [PhotonStream](#) stream, [PhotonMessageInfo](#) info)

8.45.1 Constructor & Destructor Documentation

8.45.1.1 PhotonTransformViewScaleControl.PhotonTransformViewScaleControl ([PhotonTransformViewScaleModel](#) *model*)

8.45.2 Member Function Documentation

8.45.2.1 Vector3 PhotonTransformViewScaleControl.GetNetworkScale ()

Gets the last scale that was received through the network

Returns

8.45.2.2 Vector3 PhotonTransformViewScaleControl.GetScale (Vector3 *currentScale*)

8.45.2.3 void PhotonTransformViewScaleControl.OnPhotonSerializeView (Vector3 *currentScale*, PhotonStream *stream*, PhotonMessageInfo *info*)

8.46 PhotonTransformViewScaleModel Class Reference

Public Types

- enum [InterpolateOptions](#) { [InterpolateOptions.Disabled](#), [InterpolateOptions.MoveTowards](#), [InterpolateOptions.Lerp](#) }

Public Attributes

- bool [SynchronizeEnabled](#)
- [InterpolateOptions](#) [InterpolateOption](#) = [InterpolateOptions.Disabled](#)
- float [InterpolateMoveTowardsSpeed](#) = 1f
- float [InterpolateLerpSpeed](#)

8.46.1 Member Enumeration Documentation

8.46.1.1 enum PhotonTransformViewScaleModel.InterpolateOptions

Enumerator

Disabled

MoveTowards

Lerp

8.46.2 Member Data Documentation

8.46.2.1 float PhotonTransformViewScaleModel.InterpolateLerpSpeed

8.46.2.2 float PhotonTransformViewScaleModel.InterpolateMoveTowardsSpeed = 1f

8.46.2.3 InterpolateOptions PhotonTransformViewScaleModel.InterpolateOption = InterpolateOptions.Disabled

8.46.2.4 bool PhotonTransformViewScaleModel.SynchronizeEnabled

8.47 PhotonView Class Reference

PUN's NetworkView replacement class for networking. Use it like a NetworkView.

Inherits [Photon.MonoBehaviour](#).

Public Member Functions

- void [RequestOwnership](#) ()
Depending on the [PhotonView](#)'s ownershipTransfer setting, any client can request to become owner of the [PhotonView](#).
- void [TransferOwnership](#) ([PhotonPlayer](#) newOwner)
Transfers the ownership of this [PhotonView](#) (and GameObject) to another player.
- void [TransferOwnership](#) (int newOwnerId)
Transfers the ownership of this [PhotonView](#) (and GameObject) to another player.
- void [OnMasterClientSwitched](#) ([PhotonPlayer](#) newMasterClient)
Check ownerId assignment for sceneObjects to keep being owned by the MasterClient.
- void [SerializeView](#) ([PhotonStream](#) stream, [PhotonMessageInfo](#) info)
- void [DeserializeView](#) ([PhotonStream](#) stream, [PhotonMessageInfo](#) info)
- void [RefreshRpcMonoBehaviourCache](#) ()
Can be used to refresh the list of MonoBehaviours on this GameObject while [PhotonNetwork.UseRpcMonoBehaviourCache](#) is true.
- void [RPC](#) (string methodName, [PhotonTargets](#) target, params object[] parameters)
Call a RPC method of this GameObject on remote clients of this room (or on all, including this client).
- void [RpcSecure](#) (string methodName, [PhotonTargets](#) target, bool encrypt, params object[] parameters)
Call a RPC method of this GameObject on remote clients of this room (or on all, including this client).
- void [RPC](#) (string methodName, [PhotonPlayer](#) targetPlayer, params object[] parameters)
Call a RPC method of this GameObject on remote clients of this room (or on all, including this client).
- void [RpcSecure](#) (string methodName, [PhotonPlayer](#) targetPlayer, bool encrypt, params object[] parameters)
Call a RPC method of this GameObject on remote clients of this room (or on all, including this client).
- override string [ToString](#) ()

Static Public Member Functions

- static [PhotonView](#) [Get](#) (Component component)
- static [PhotonView](#) [Get](#) (GameObject gameObj)
- static [PhotonView](#) [Find](#) (int viewID)

Public Attributes

- int [ownerId](#)
- byte [group](#) = 0
- bool [OwnershipWasTransferred](#)
Flag to check if ownership of this photonView was set during the lifecycle. Used for checking when joining late if event with mismatched owner and sender needs addressing.
- int [prefixBackup](#) = -1
- [ViewSynchronization](#) [synchronization](#)
- [OnSerializeTransform](#) [onSerializeTransformOption](#) = [OnSerializeTransform.PositionAndRotation](#)
- [OnSerializeRigidBody](#) [onSerializeRigidBodyOption](#) = [OnSerializeRigidBody.All](#)
- [OwnershipOption](#) [ownershipTransfer](#) = [OwnershipOption.Fixed](#)
Defines if ownership of this [PhotonView](#) is fixed, can be requested or simply taken.
- List< Component > [ObservedComponents](#)
- int [instantiationId](#)
- int [currentMasterID](#) = -1
The current master ID so that we can compare when we receive [OnMasterClientSwitched\(\)](#) callback It's public so that we can check it during ownerId assignments in networkPeer script TODO: Maybe we can have the networkPeer always aware of the previous MasterClient?

Properties

- int [prefix](#) [get, set]
- object[] [instantiationData](#) [get, set]
This is the instantiationData that was passed when calling [PhotonNetwork.Instantiate](#) (if that was used to spawn this prefab)*
- int [viewID](#) [get, set]
The ID of the [PhotonView](#). Identifies it in a networked game (per room).
- bool [isSceneView](#) [get]
True if the [PhotonView](#) was loaded with the scene (game object) or instantiated with [InstantiateSceneObject](#).
- [PhotonPlayer](#) owner [get]
The owner of a [PhotonView](#) is the player who created the GameObject with that view. Objects in the scene don't have an owner.
- int [OwnerActorNr](#) [get]
- bool [isOwnerActive](#) [get]
- int [CreatorActorNr](#) [get]
- bool [isMine](#) [get]
True if the [PhotonView](#) is "mine" and can be controlled by this client.

8.47.1 Detailed Description

PUN's NetworkView replacement class for networking. Use it like a NetworkView.

8.47.2 Member Function Documentation

8.47.2.1 void [PhotonView.DeserializeView](#) ([PhotonStream](#) *stream*, [PhotonMessageInfo](#) *info*)

8.47.2.2 static [PhotonView](#) [PhotonView.Find](#) (int *viewID*) [static]

8.47.2.3 static [PhotonView](#) [PhotonView.Get](#) ([Component](#) *component*) [static]

8.47.2.4 static [PhotonView](#) [PhotonView.Get](#) ([GameObject](#) *gameObj*) [static]

8.47.2.5 void [PhotonView.OnMasterClientSwitched](#) ([PhotonPlayer](#) *newMasterClient*)

Check ownerId assignment for sceneObjects to keep being owned by the MasterClient.

Parameters

<i>newMasterClient</i>	New master client.
------------------------	--------------------

8.47.2.6 void [PhotonView.RefreshRpcMonoBehaviourCache](#) ()

Can be used to refresh the list of MonoBehaviours on this GameObject while [PhotonNetwork.UseRpcMonoBehaviourCache](#) is true.

Set [PhotonNetwork.UseRpcMonoBehaviourCache](#) to true to enable the caching. Uses [this.GetComponents<MonoBehaviour>\(\)](#) to get a list of MonoBehaviours to call RPCs on (potentially).

While [PhotonNetwork.UseRpcMonoBehaviourCache](#) is false, this method has no effect, because the list is refreshed when a RPC gets called.

8.47.2.7 void PhotonView.RequestOwnership ()

Depending on the [PhotonView](#)'s ownershipTransfer setting, any client can request to become owner of the [PhotonView](#).

Requesting ownership can give you control over a [PhotonView](#), if the ownershipTransfer setting allows that. The current owner might have to implement [IPunCallbacks.OnOwnershipRequest](#) to react to the ownership request.

The owner/controller of a [PhotonView](#) is also the client which sends position updates of the GameObject.

8.47.2.8 void PhotonView.RPC (string methodName, PhotonTargets target, params object[] parameters)

Call a RPC method of this GameObject on remote clients of this room (or on all, including this client).

[Remote Procedure Calls](#) are an essential tool in making multiplayer games with PUN. It enables you to make every client in a room call a specific method.

RPC calls can target "All" or the "Others". Usually, the target "All" gets executed locally immediately after sending the RPC. The "*ViaServer" options send the RPC to the server and execute it on this client when it's sent back. Of course, calls are affected by this client's lag and that of remote clients.

Each call automatically is routed to the same [PhotonView](#) (and GameObject) that was used on the originating client.

See: [Remote Procedure Calls](#).

Parameters

<i>methodName</i>	The name of a fitting method that was has the RPC attribute.
<i>target</i>	The group of targets and the way the RPC gets sent.
<i>parameters</i>	The parameters that the RPC method has (must fit this call!).

8.47.2.9 void PhotonView.RPC (string methodName, PhotonPlayer targetPlayer, params object[] parameters)

Call a RPC method of this GameObject on remote clients of this room (or on all, including this client).

[Remote Procedure Calls](#) are an essential tool in making multiplayer games with PUN. It enables you to make every client in a room call a specific method.

This method allows you to make an RPC calls on a specific player's client. Of course, calls are affected by this client's lag and that of remote clients.

Each call automatically is routed to the same [PhotonView](#) (and GameObject) that was used on the originating client.

See: [Remote Procedure Calls](#).

Parameters

<i>methodName</i>	The name of a fitting method that was has the RPC attribute.
<i>targetPlayer</i>	The group of targets and the way the RPC gets sent.
<i>parameters</i>	The parameters that the RPC method has (must fit this call!).

8.47.2.10 void PhotonView.RpcSecure (string methodName, PhotonTargets target, bool encrypt, params object[] parameters)

Call a RPC method of this GameObject on remote clients of this room (or on all, including this client).

[Remote Procedure Calls](#) are an essential tool in making multiplayer games with PUN. It enables you to make every client in a room call a specific method.

RPC calls can target "All" or the "Others". Usually, the target "All" gets executed locally immediately after sending the RPC. The "*ViaServer" options send the RPC to the server and execute it on this client when it's sent back. Of course, calls are affected by this client's lag and that of remote clients.

Each call automatically is routed to the same [PhotonView](#) (and [GameObject](#)) that was used on the originating client.

See: [Remote Procedure Calls](#).

param name="methodName">The name of a fitting method that was has the RPC attribute.

param name="target">The group of targets and the way the RPC gets sent.

param name="encrypt">

param name="parameters">The parameters that the RPC method has (must fit this call!).

8.47.2.11 `void PhotonView.RpcSecure (string methodName, PhotonPlayer targetPlayer, bool encrypt, params object[] parameters)`

Call a RPC method of this [GameObject](#) on remote clients of this room (or on all, including this client).

[Remote Procedure Calls](#) are an essential tool in making multiplayer games with PUN. It enables you to make every client in a room call a specific method.

This method allows you to make an RPC calls on a specific player's client. Of course, calls are affected by this client's lag and that of remote clients.

Each call automatically is routed to the same [PhotonView](#) (and [GameObject](#)) that was used on the originating client.

See: [Remote Procedure Calls](#).

param name="methodName">The name of a fitting method that was has the RPC attribute.

param name="targetPlayer">The group of targets and the way the RPC gets sent.

param name="encrypt">

param name="parameters">The parameters that the RPC method has (must fit this call!).

8.47.2.12 `void PhotonView.SerializeView (PhotonStream stream, PhotonMessageInfo info)`

8.47.2.13 `override string PhotonView.ToString ()`

8.47.2.14 `void PhotonView.TransferOwnership (PhotonPlayer newOwner)`

Transfers the ownership of this [PhotonView](#) (and [GameObject](#)) to another player.

The owner/controller of a [PhotonView](#) is also the client which sends position updates of the [GameObject](#).

8.47.2.15 `void PhotonView.TransferOwnership (int newOwnerId)`

Transfers the ownership of this [PhotonView](#) (and [GameObject](#)) to another player.

The owner/controller of a [PhotonView](#) is also the client which sends position updates of the [GameObject](#).

8.47.3 Member Data Documentation

8.47.3.1 `int PhotonView.currentMasterID = -1`

The current master ID so that we can compare when we receive [OnMasterClientSwitched\(\)](#) callback It's public so that we can check it during ownerId assignments in networkPeer script TODO: Maybe we can have the networkPeer always aware of the previous MasterClient?

8.47.3.2 `byte PhotonView.group = 0`

8.47.3.3 `int PhotonView.instantiateId`

8.47.3.4 `List<Component> PhotonView.ObservedComponents`

8.47.3.5 `OnSerializeRigidBody PhotonView.onSerializeRigidBodyOption = OnSerializeRigidBody.All`

8.47.3.6 `OnSerializeTransform PhotonView.onSerializeTransformOption = OnSerializeTransform.PositionAndRotation`

8.47.3.7 `int PhotonView.ownerId`

8.47.3.8 `OwnershipOption PhotonView.ownershipTransfer = OwnershipOption.Fixed`

Defines if ownership of this [PhotonView](#) is fixed, can be requested or simply taken.

Note that you can't edit this value at runtime. The options are described in enum `OwnershipOption`. The current owner has to implement [IPunCallbacks.OnOwnershipRequest](#) to react to the ownership request.

8.47.3.9 `bool PhotonView.OwnerShipWasTransferred`

Flag to check if ownership of this `PhotonView` was set during the lifecycle. Used for checking when joining late if event with mismatched owner and sender needs addressing.

`true` if owner ship was transferred; otherwise, `false`.

8.47.3.10 `int PhotonView.prefixBackup = -1`

8.47.3.11 `ViewSynchronization PhotonView.synchronization`

8.47.4 Property Documentation

8.47.4.1 `int PhotonView.CreatorActorNr` `[get]`

8.47.4.2 `object[] PhotonView.instantiateData` `[get], [set]`

This is the `instantiateData` that was passed when calling [PhotonNetwork.Instantiate*](#) (if that was used to spawn this prefab)

8.47.4.3 `bool PhotonView.isMine` `[get]`

True if the [PhotonView](#) is "mine" and can be controlled by this client.

PUN has an ownership concept that defines who can control and destroy each [PhotonView](#). True in case the owner matches the local [PhotonPlayer](#). True if this is a scene `PhotonView` on the Master client.

8.47.4.4 `bool PhotonView.isOwnerActive` `[get]`

8.47.4.5 `bool PhotonView.isSceneView` `[get]`

True if the [PhotonView](#) was loaded with the scene (game object) or instantiated with `InstantiateSceneObject`.

Scene objects are not owned by a particular player but belong to the scene. Thus they don't get destroyed when their creator leaves the game and the current Master Client can control them (whoever that is). The `ownerId` is 0 (player IDs are 1 and up).

8.47.4.6 PhotonPlayer PhotonView.owner [get]

The owner of a [PhotonView](#) is the player who created the GameObject with that view. Objects in the scene don't have an owner.

The owner/controller of a [PhotonView](#) is also the client which sends position updates of the GameObject.

Ownership can be transferred to another player with [PhotonView.TransferOwnership](#) or any player can request ownership by calling the [PhotonView](#)'s RequestOwnership method. The current owner has to implement [IPunCallbacks.OnOwnershipRequest](#) to react to the ownership request.

8.47.4.7 int PhotonView.OwnerActorNr [get]

8.47.4.8 int PhotonView.prefix [get], [set]

8.47.4.9 int PhotonView.viewID [get], [set]

The ID of the [PhotonView](#). Identifies it in a networked game (per room).

See: [Network Instantiation](#)

8.48 PhotonMonoEditor Class Reference

Uses C# Socket class from System.Net.Sockets (as Unity usually does).

Inherits PhotonPing.

Public Member Functions

- override bool [StartPing](#) (string ip)
Sends a "Photon Ping" to a server.
- override bool [Done](#) ()
- override void [Dispose](#) ()

8.48.1 Detailed Description

Uses C# Socket class from System.Net.Sockets (as Unity usually does).

Incompatible with Windows 8 Store/Phone API.

8.48.2 Member Function Documentation

8.48.2.1 override void PhotonMonoEditor.Dispose ()

8.48.2.2 override bool PhotonMonoEditor.Done ()

8.48.2.3 override bool PhotonMonoEditor.StartPing (string ip)

Sends a "Photon Ping" to a server.

Parameters

<i>ip</i>	Address in IPv4 or IPv6 format. An address containing a '.' will be interpreted as IPv4.
-----------	--

Returns

True if the [Photon](#) Ping could be sent.

8.49 Photon.PunBehaviour Class Reference

This class provides a `.photonView` and all callbacks/events that PUN can call. Override the events/methods you want to use.

Inherits [Photon.MonoBehaviour](#), and [IPunCallbacks](#).

Public Member Functions

- virtual void [OnConnectedToPhoton](#) ()
Called when the initial connection got established but before you can use the server. [OnJoinedLobby\(\)](#) or [OnConnectedToMaster\(\)](#) are called when PUN is ready.
- virtual void [OnLeftRoom](#) ()
Called when the local user/client left a room.
- virtual void [OnMasterClientSwitched](#) ([PhotonPlayer](#) newMasterClient)
Called after switching to a new MasterClient when the current one leaves.
- virtual void [OnPhotonCreateRoomFailed](#) (object[] codeAndMsg)
Called when a [CreateRoom\(\)](#) call failed. The parameter provides [ErrorCode](#) and message (as array).
- virtual void [OnPhotonJoinRoomFailed](#) (object[] codeAndMsg)
Called when a [JoinRoom\(\)](#) call failed. The parameter provides [ErrorCode](#) and message (as array).
- virtual void [OnCreatedRoom](#) ()
Called when this client created a room and entered it. [OnJoinedRoom\(\)](#) will be called as well.
- virtual void [OnJoinedLobby](#) ()
Called on entering a lobby on the Master Server. The actual room-list updates will call [OnReceivedRoomListUpdate\(\)](#).
- virtual void [OnLeftLobby](#) ()
Called after leaving a lobby.
- virtual void [OnFailedToConnectToPhoton](#) ([DisconnectCause](#) cause)
Called if a connect call to the [Photon](#) server failed before the connection was established, followed by a call to [OnDisconnectedFromPhoton\(\)](#).
- virtual void [OnDisconnectedFromPhoton](#) ()
Called after disconnecting from the [Photon](#) server.
- virtual void [OnConnectionFail](#) ([DisconnectCause](#) cause)
Called when something causes the connection to fail (after it was established), followed by a call to [OnDisconnectedFromPhoton\(\)](#).
- virtual void [OnPhotonInstantiate](#) ([PhotonMessageInfo](#) info)
Called on all scripts on a GameObject (and children) that have been instantiated using [PhotonNetwork.Instantiate](#).
- virtual void [OnReceivedRoomListUpdate](#) ()
Called for any update of the room-listing while in a lobby ([PhotonNetwork.insideLobby](#)) on the Master Server.
- virtual void [OnJoinedRoom](#) ()
Called when entering a room (by creating or joining it). Called on all clients (including the Master Client).
- virtual void [OnPhotonPlayerConnected](#) ([PhotonPlayer](#) newPlayer)
Called when a remote player entered the room. This [PhotonPlayer](#) is already added to the playerlist at this time.
- virtual void [OnPhotonPlayerDisconnected](#) ([PhotonPlayer](#) otherPlayer)
Called when a remote player left the room. This [PhotonPlayer](#) is already removed from the playerlist at this time.
- virtual void [OnPhotonRandomJoinFailed](#) (object[] codeAndMsg)

- Called when a `JoinRandom()` call failed. The parameter provides [ErrorCode](#) and message.*

 - virtual void [OnConnectedToMaster](#) ()

Called after the connection to the master is established and authenticated but only when [PhotonNetwork.autoJoinLobby](#) is false.
- virtual void [OnPhotonMaxCccuReached](#) ()

Because the concurrent user limit was (temporarily) reached, this client is rejected by the server and disconnecting.
- virtual void [OnPhotonCustomRoomPropertiesChanged](#) (Hashtable propertiesThatChanged)

Called when a room's custom properties changed. The `propertiesThatChanged` contains all that was set via [Room.SetCustomProperties](#).
- virtual void [OnPhotonPlayerPropertiesChanged](#) (object[] playerAndUpdatedProps)

Called when custom player-properties are changed. Player and the changed properties are passed as `object[]`.
- virtual void [OnUpdatedFriendList](#) ()

Called when the server sent the response to a `FindFriends` request and updated [PhotonNetwork.Friends](#).
- virtual void [OnCustomAuthenticationFailed](#) (string debugMessage)

Called when the custom authentication failed. Followed by disconnect!
- virtual void [OnCustomAuthenticationResponse](#) (Dictionary< string, object > data)

Called when your Custom Authentication service responds with additional data.
- virtual void [OnWebRpcResponse](#) (OperationResponse response)

Called by PUN when the response to a `WebRPC` is available. See [PhotonNetwork.WebRPC](#).
- virtual void [OnOwnershipRequest](#) (object[] viewAndPlayer)

Called when another player requests ownership of a [PhotonView](#) from you (the current owner).
- virtual void [OnLobbyStatisticsUpdate](#) ()

Called when the Master Server sent an update for the Lobby Statistics, updating [PhotonNetwork.LobbyStatistics](#).
- virtual void [OnPhotonPlayerActivityChanged](#) (PhotonPlayer otherPlayer)

Called when a remote [Photon](#) Player activity changed. This will be called ONLY if `PlayerTtl` is greater than 0.
- virtual void [OnOwnershipTransferred](#) (object[] viewAndPlayers)

Called when ownership of a [PhotonView](#) is transferred to another player.

Additional Inherited Members

8.49.1 Detailed Description

This class provides a `.photonView` and all callbacks/events that PUN can call. Override the events/methods you want to use.

By extending this class, you can implement individual methods as override.

Visual Studio and MonoDevelop should provide the list of methods when you begin typing "override". **Your implementation does not have to call "base.method()".**

This class implements [IPunCallbacks](#), which is used as definition of all PUN callbacks. Don't implement [IPunCallbacks](#) in your classes. Instead, implement [PunBehaviour](#) or individual methods.

8.49.2 Member Function Documentation

8.49.2.1 virtual void Photon.PunBehaviour.OnConnectedToMaster () [virtual]

Called after the connection to the master is established and authenticated but only when [PhotonNetwork.autoJoinLobby](#) is false.

If you set [PhotonNetwork.autoJoinLobby](#) to true, [OnJoinedLobby\(\)](#) will be called instead of this.

You can join rooms and create them even without being in a lobby. The default lobby is used in that case. The list of available rooms won't become available unless you join a lobby via [PhotonNetwork.joinLobby](#).

Implements [IPunCallbacks](#).

8.49.2.2 virtual void Photon.PunBehaviour.OnConnectedToPhoton () [virtual]

Called when the initial connection got established but before you can use the server. [OnJoinedLobby\(\)](#) or [OnConnectedToMaster\(\)](#) are called when PUN is ready.

This callback is only useful to detect if the server can be reached at all (technically). Most often, it's enough to implement [OnFailedToConnectToPhoton\(\)](#) and [OnDisconnectedFromPhoton\(\)](#).

[OnJoinedLobby\(\)](#) or [OnConnectedToMaster\(\)](#) are called when PUN is ready.

When this is called, the low level connection is established and PUN will send your AppId, the user, etc in the background. This is not called for transitions from the masterserver to game servers.

Implements [IPunCallbacks](#).

8.49.2.3 virtual void Photon.PunBehaviour.OnConnectionFail (DisconnectCause cause) [virtual]

Called when something causes the connection to fail (after it was established), followed by a call to [OnDisconnectedFromPhoton\(\)](#).

If the server could not be reached in the first place, [OnFailedToConnectToPhoton](#) is called instead. The reason for the error is provided as [DisconnectCause](#).

Implements [IPunCallbacks](#).

8.49.2.4 virtual void Photon.PunBehaviour.OnCreatedRoom () [virtual]

Called when this client created a room and entered it. [OnJoinedRoom\(\)](#) will be called as well.

This callback is only called on the client which created a room (see [PhotonNetwork.CreateRoom](#)).

As any client might close (or drop connection) anytime, there is a chance that the creator of a room does not execute [OnCreatedRoom](#).

If you need specific room properties or a "start signal", it is safer to implement [OnMasterClientSwitched\(\)](#) and to make the new [MasterClient](#) check the room's state.

Implements [IPunCallbacks](#).

8.49.2.5 virtual void Photon.PunBehaviour.OnCustomAuthenticationFailed (string debugMessage) [virtual]

Called when the custom authentication failed. Followed by disconnect!

Custom Authentication can fail due to user-input, bad tokens/secrets. If authentication is successful, this method is not called. Implement [OnJoinedLobby\(\)](#) or [OnConnectedToMaster\(\)](#) (as usual).

During development of a game, it might also fail due to wrong configuration on the server side. In those cases, logging the [debugMessage](#) is very important.

Unless you setup a custom authentication service for your app (in the [Dashboard](#)), this won't be called!

Parameters

<i>debugMessage</i>	Contains a debug message why authentication failed. This has to be fixed during development time.
---------------------	---

Implements [IPunCallbacks](#).

8.49.2.6 virtual void Photon.PunBehaviour.OnCustomAuthenticationResponse (Dictionary< string, object > data) [virtual]

Called when your Custom Authentication service responds with additional data.

Custom Authentication services can include some custom data in their response. When present, that data is made available in this callback as Dictionary. While the keys of your data have to be strings, the values can be either string or a number (in Json). You need to make extra sure, that the value type is the one you expect. Numbers become (currently) int64.

Example: void OnCustomAuthenticationResponse(Dictionary<string, object> data) { ... }

<https://doc.photonengine.com/en/realtime/current/reference/custom-authentication>

Implements [IPunCallbacks](#).

8.49.2.7 virtual void Photon.PunBehaviour.OnDisconnectedFromPhoton () [virtual]

Called after disconnecting from the [Photon](#) server.

In some cases, other callbacks are called before OnDisconnectedFromPhoton is called. Examples: [OnConnectionFail\(\)](#) and [OnFailedToConnectToPhoton\(\)](#).

Implements [IPunCallbacks](#).

8.49.2.8 virtual void Photon.PunBehaviour.OnFailedToConnectToPhoton (DisconnectCause *cause*) [virtual]

Called if a connect call to the [Photon](#) server failed before the connection was established, followed by a call to [OnDisconnectedFromPhoton\(\)](#).

This is called when no connection could be established at all. It differs from OnConnectionFail, which is called when an existing connection fails.

Implements [IPunCallbacks](#).

8.49.2.9 virtual void Photon.PunBehaviour.OnJoinedLobby () [virtual]

Called on entering a lobby on the Master Server. The actual room-list updates will call [OnReceivedRoomListUpdate\(\)](#).

Note: When [PhotonNetwork.autoJoinLobby](#) is false, [OnConnectedToMaster\(\)](#) will be called and the room list won't become available.

While in the lobby, the roomlist is automatically updated in fixed intervals (which you can't modify). The room list gets available when [OnReceivedRoomListUpdate\(\)](#) gets called after [OnJoinedLobby\(\)](#).

Implements [IPunCallbacks](#).

8.49.2.10 virtual void Photon.PunBehaviour.OnJoinedRoom () [virtual]

Called when entering a room (by creating or joining it). Called on all clients (including the Master Client).

This method is commonly used to instantiate player characters. If a match has to be started "actively", you can call an [PunRPC](#) triggered by a user's button-press or a timer.

When this is called, you can usually already access the existing players in the room via [PhotonNetwork.playerList](#). Also, all custom properties should be already available as [Room.customProperties](#). Check [Room.playerCount](#) to find out if enough players are in the room to start playing.

Implements [IPunCallbacks](#).

8.49.2.11 virtual void Photon.PunBehaviour.OnLeftLobby () [virtual]

Called after leaving a lobby.

When you leave a lobby, [CreateRoom](#) and [JoinRandomRoom](#) automatically refer to the default lobby.

Implements [IPunCallbacks](#).

8.49.2.12 `virtual void Photon.PunBehaviour.OnLeftRoom () [virtual]`

Called when the local user/client left a room.

When leaving a room, PUN brings you back to the Master Server. Before you can use lobbies and join or create rooms, [OnJoinedLobby\(\)](#) or [OnConnectedToMaster\(\)](#) will get called again.

Implements [IPunCallbacks](#).

8.49.2.13 `virtual void Photon.PunBehaviour.OnLobbyStatisticsUpdate () [virtual]`

Called when the Master Server sent an update for the Lobby Statistics, updating [PhotonNetwork.LobbyStatistics](#).

This callback has two preconditions: `EnableLobbyStatistics` must be set to true, before this client connects. And the client has to be connected to the Master Server, which is providing the info about lobbies.

Implements [IPunCallbacks](#).

8.49.2.14 `virtual void Photon.PunBehaviour.OnMasterClientSwitched (PhotonPlayer newMasterClient) [virtual]`

Called after switching to a new MasterClient when the current one leaves.

This is not called when this client enters a room. The former MasterClient is still in the player list when this method get called.

Implements [IPunCallbacks](#).

8.49.2.15 `virtual void Photon.PunBehaviour.OnOwnershipRequest (object[] viewAndPlayer) [virtual]`

Called when another player requests ownership of a [PhotonView](#) from you (the current owner).

The parameter `viewAndPlayer` contains:

[PhotonView](#) `view` = `viewAndPlayer[0]` as [PhotonView](#);

[PhotonPlayer](#) `requestingPlayer` = `viewAndPlayer[1]` as [PhotonPlayer](#);

Parameters

<i>viewAndPlayer</i>	The PhotonView is <code>viewAndPlayer[0]</code> and the requesting player is <code>viewAndPlayer[1]</code> .
----------------------	--

Implements [IPunCallbacks](#).

8.49.2.16 `virtual void Photon.PunBehaviour.OnOwnershipTransferred (object[] viewAndPlayers) [virtual]`

Called when ownership of a [PhotonView](#) is transferred to another player.

The parameter `viewAndPlayers` contains:

[PhotonView](#) `view` = `viewAndPlayers[0]` as [PhotonView](#);

[PhotonPlayer](#) `newOwner` = `viewAndPlayers[1]` as [PhotonPlayer](#);

[PhotonPlayer](#) `oldOwner` = `viewAndPlayers[2]` as [PhotonPlayer](#);

`void OnOwnershipTransferred(object[] viewAndPlayers) {} //`

Implements [IPunCallbacks](#).

8.49.2.17 `virtual void Photon.PunBehaviour.OnPhotonCreateRoomFailed (object[] codeAndMsg) [virtual]`

Called when a [CreateRoom\(\)](#) call failed. The parameter provides [ErrorCode](#) and message (as array).

Most likely because the room name is already in use (some other client was faster than you). PUN logs some info if the [PhotonNetwork.logLevel](#) is \geq `PhotonLogLevel.Informational`.

Parameters

<i>codeAndMsg</i>	<code>codeAndMsg[0]</code> is a short ErrorCode and <code>codeAndMsg[1]</code> is a string debug msg.
-------------------	---

Implements [IPunCallbacks](#).

8.49.2.18 `virtual void Photon.PunBehaviour.OnPhotonCustomRoomPropertiesChanged (Hashtable propertiesThatChanged) [virtual]`

Called when a room's custom properties changed. The `propertiesThatChanged` contains all that was set via [Room.SetCustomProperties](#).

Since v1.25 this method has one parameter: `Hashtable propertiesThatChanged`.

Changing properties must be done by [Room.SetCustomProperties](#), which causes this callback locally, too.

Parameters

<i>propertiesThatChanged</i>	
------------------------------	--

Implements [IPunCallbacks](#).

8.49.2.19 `virtual void Photon.PunBehaviour.OnPhotonInstantiate (PhotonMessageInfo info) [virtual]`

Called on all scripts on a `GameObject` (and children) that have been instantiated using [PhotonNetwork.Instantiate](#). [PhotonMessageInfo](#) parameter provides info about who created the object and when (based off `PhotonNetwork.time`).

Implements [IPunCallbacks](#).

8.49.2.20 `virtual void Photon.PunBehaviour.OnPhotonJoinRoomFailed (object[] codeAndMsg) [virtual]`

Called when a [JoinRoom\(\)](#) call failed. The parameter provides [ErrorCode](#) and message (as array).

Most likely error is that the room does not exist or the room is full (some other client was faster than you). PUN logs some info if the [PhotonNetwork.logLevel](#) is \geq `PhotonLogLevel.Informational`.

Parameters

<i>codeAndMsg</i>	<code>codeAndMsg[0]</code> is short ErrorCode . <code>codeAndMsg[1]</code> is string debug msg.
-------------------	---

Implements [IPunCallbacks](#).

8.49.2.21 `virtual void Photon.PunBehaviour.OnPhotonMaxCcuReached () [virtual]`

Because the concurrent user limit was (temporarily) reached, this client is rejected by the server and disconnecting.

When this happens, the user might try again later. You can't create or join rooms in `OnPhotonMaxCcuReached()`, cause the client will be disconnecting. You can raise the CCU limits with a new license (when you host yourself) or extended subscription (when using the [Photon Cloud](#)). The [Photon Cloud](#) will mail you when the CCU limit was reached. This is also visible in the Dashboard (webpage).

Implements [IPunCallbacks](#).

8.49.2.22 `virtual void Photon.PunBehaviour.OnPhotonPlayerActivityChanged (PhotonPlayer otherPlayer) [virtual]`

Called when a remote [Photon](#) Player activity changed. This will be called ONLY if PlayerTtl is greater than 0.

Use [PhotonPlayer.IsInactive](#) to check a player's current activity state.

Example: `void OnPhotonPlayerActivityChanged(PhotonPlayer otherPlayer) {...}`

This callback has precondition: PlayerTtl must be greater than 0.

Implements [IPunCallbacks](#).

8.49.2.23 `virtual void Photon.PunBehaviour.OnPhotonPlayerConnected (PhotonPlayer newPlayer) [virtual]`

Called when a remote player entered the room. This [PhotonPlayer](#) is already added to the playerlist at this time.

If your game starts with a certain number of players, this callback can be useful to check the [Room.playerCount](#) and find out if you can start.

Implements [IPunCallbacks](#).

8.49.2.24 `virtual void Photon.PunBehaviour.OnPhotonPlayerDisconnected (PhotonPlayer otherPlayer) [virtual]`

Called when a remote player left the room. This [PhotonPlayer](#) is already removed from the playerlist at this time.

When your client calls [PhotonNetwork.leaveRoom](#), PUN will call this method on the remaining clients. When a remote client drops connection or gets closed, this callback gets executed. after a timeout of several seconds.

Implements [IPunCallbacks](#).

8.49.2.25 `virtual void Photon.PunBehaviour.OnPhotonPlayerPropertiesChanged (object[] playerAndUpdatedProps) [virtual]`

Called when custom player-properties are changed. Player and the changed properties are passed as `object[]`.

Since v1.25 this method has one parameter: `object[] playerAndUpdatedProps`, which contains two entries.

[0] is the affected [PhotonPlayer](#).

[1] is the Hashtable of properties that changed.

We are using a `object[]` due to limitations of Unity's `GameObject.SendMessage` (which has only one optional parameter).

Changing properties must be done by [PhotonPlayer.SetCustomProperties](#), which causes this callback locally, too.

Example:

```
void OnPhotonPlayerPropertiesChanged(object[] playerAndUpdatedProps) {
    PhotonPlayer player = playerAndUpdatedProps[0] as PhotonPlayer;
    Hashtable props = playerAndUpdatedProps[1] as Hashtable;
    //...
}
```

Parameters

<i>playerAndUpdatedProps</i>	Contains PhotonPlayer and the properties that changed See remarks.
------------------------------	--

Implements [IPunCallbacks](#).

8.49.2.26 `virtual void Photon.PunBehaviour.OnPhotonRandomJoinFailed (object[] codeAndMsg) [virtual]`

Called when a `JoinRandom()` call failed. The parameter provides [ErrorCode](#) and message.

Most likely all rooms are full or no rooms are available.

When using multiple lobbies (via [JoinLobby](#) or [TypedLobby](#)), another lobby might have more/fitting rooms.

PUN logs some info if the [PhotonNetwork.logLevel](#) is \geq [PhotonLogLevel.Informational](#).

Parameters

<i>codeAndMsg</i>	<i>codeAndMsg[0]</i> is short ErrorCode . <i>codeAndMsg[1]</i> is string debug msg.
-------------------	---

Implements [IPunCallbacks](#).

8.49.2.27 virtual void Photon.PunBehaviour.OnReceivedRoomListUpdate () [virtual]

Called for any update of the room-listing while in a lobby ([PhotonNetwork.insideLobby](#)) on the Master Server.

PUN provides the list of rooms by [PhotonNetwork.GetRoomList\(\)](#).

Each item is a [RoomInfo](#) which might include custom properties (provided you defined those as lobby-listed when creating a room).

Not all types of lobbies provide a listing of rooms to the client. Some are silent and specialized for server-side matchmaking.

Implements [IPunCallbacks](#).

8.49.2.28 virtual void Photon.PunBehaviour.OnUpdatedFriendList () [virtual]

Called when the server sent the response to a FindFriends request and updated [PhotonNetwork.Friends](#).

The friends list is available as [PhotonNetwork.Friends](#), listing name, online state and the room a user is in (if any).

Implements [IPunCallbacks](#).

8.49.2.29 virtual void Photon.PunBehaviour.OnWebRpcResponse (*OperationResponse response*) [virtual]

Called by PUN when the response to a WebRPC is available. See [PhotonNetwork.WebRPC](#).

Important: The response.ReturnCode is 0 if [Photon](#) was able to reach your web-service. The content of the response is what your web-service sent. You can create a [WebResponse](#) instance from it. Example: [WebRpcResponse](#) webResponse = new [WebRpcResponse\(operationResponse\)](#);

Please note: Class [OperationResponse](#) is in a namespace which needs to be "used": using [ExitGames.Client.Photon](#); // includes [OperationResponse](#) (and other classes)

The [OperationResponse.ReturnCode](#) by [Photon](#) is:

```
0 for "OK"
-3 for "Web-Service not configured" (see Dashboard / WebHooks)
-5 for "Web-Service does now have RPC path/name" (at least for Azure)
```

Implements [IPunCallbacks](#).

8.50 PunRPC Class Reference

Replacement for [RPC](#) attribute with different name. Used to flag methods as remote-callable.

Inherits [Attribute](#).

8.50.1 Detailed Description

Replacement for [RPC](#) attribute with different name. Used to flag methods as remote-callable.

8.51 RaiseEventOptions Class Reference

Aggregates several less-often used options for operation RaiseEvent. See field descriptions for usage details.

Public Attributes

- [EventCaching CachingOption](#)
Defines if the server should simply send the event, put it in the cache or remove events that are like this one.
- `byte` [InterestGroup](#)
The number of the Interest Group to send this to. 0 goes to all users but to get 1 and up, clients must subscribe to the group first.
- `int[]` [TargetActors](#)
A list of PhotonPlayer.IDs to send this event to. You can implement events that just go to specific users this way.
- [ReceiverGroup Receivers](#)
Sends the event to All, MasterClient or Others (default). Be careful with MasterClient, as the client might disconnect before it got the event and it gets lost.
- `byte` [SequenceChannel](#)
Events are ordered per "channel". If you have events that are independent of others, they can go into another sequence or channel.
- `bool` [ForwardToWebhook](#)
Events can be forwarded to Webhooks, which can evaluate and use the events to follow the game's state.
- `bool` [Encrypt](#)

Static Public Attributes

- `static readonly` [RaiseEventOptions Default](#) = `new RaiseEventOptions()`
Default options: CachingOption: DoNotCache, InterestGroup: 0, targetActors: null, receivers: Others, sequence↔ Channel: 0.

8.51.1 Detailed Description

Aggregates several less-often used options for operation RaiseEvent. See field descriptions for usage details.

8.51.2 Member Data Documentation

8.51.2.1 EventCaching RaiseEventOptions.CachingOption

Defines if the server should simply send the event, put it in the cache or remove events that are like this one.

When using option: SliceSetIndex, SlicePurgeIndex or SlicePurgeUpToIndex, set a CacheSliceIndex. All other options except SequenceChannel get ignored.

8.51.2.2 `readonly RaiseEventOptions RaiseEventOptions.Default = new RaiseEventOptions()` [static]

Default options: CachingOption: DoNotCache, InterestGroup: 0, targetActors: null, receivers: Others, sequence↔ Channel: 0.

8.51.2.3 `bool RaiseEventOptions.Encrypt`

8.51.2.4 `bool RaiseEventOptions.ForwardToWebhook`

Events can be forwarded to Webhooks, which can evaluate and use the events to follow the game's state.

8.51.2.5 `byte RaiseEventOptions.InterestGroup`

The number of the Interest Group to send this to. 0 goes to all users but to get 1 and up, clients must subscribe to the group first.

8.51.2.6 `ReceiverGroup RaiseEventOptions.Receivers`

Sends the event to All, MasterClient or Others (default). Be careful with MasterClient, as the client might disconnect before it got the event and it gets lost.

8.51.2.7 `byte RaiseEventOptions.SequenceChannel`

Events are ordered per "channel". If you have events that are independent of others, they can go into another sequence or channel.

8.51.2.8 `int [] RaiseEventOptions.TargetActors`

A list of PhotonPlayer.IDs to send this event to. You can implement events that just go to specific users this way.

8.52 Region Class Reference

Public Member Functions

- [Region](#) ([CloudRegionCode](#) code)
- [Region](#) ([CloudRegionCode](#) code, string regionCodeString, string address)
- override string [ToString](#) ()

Static Public Member Functions

- static [CloudRegionCode Parse](#) (string codeAsString)

Public Attributes

- [CloudRegionCode Code](#)
- string [Cluster](#)
Unlike the CloudRegionCode, this may contain cluster information.
- string [HostAndPort](#)
- int [Ping](#)

8.52.1 Constructor & Destructor Documentation

8.52.1.1 `Region.Region (CloudRegionCode code)`

8.52.1.2 `Region.Region (CloudRegionCode code, string regionCodeString, string address)`

8.52.2 Member Function Documentation

8.52.2.1 `static CloudRegionCode Region.Parse (string codeAsString)` [*static*]

8.52.2.2 `override string Region.ToString ()`

8.52.3 Member Data Documentation

8.52.3.1 string Region.Cluster

Unlike the CloudRegionCode, this may contain cluster information.

8.52.3.2 CloudRegionCode Region.Code

8.52.3.3 string Region.HostAndPort

8.52.3.4 int Region.Ping

8.53 Room Class Reference

This class resembles a room that PUN joins (or joined). The properties are settable as opposed to those of a [RoomInfo](#) and you can close or hide "your" room.

Inherits [RoomInfo](#).

Public Member Functions

- void [SetCustomProperties](#) ([Hashtable](#) propertiesToSet, [Hashtable](#) expectedValues=null, bool web↔Forward=false)
Updates the current room's Custom Properties with new/updated key-values.
- void [SetPropertiesListedInLobby](#) (string[] propsListedInLobby)
Enables you to define the properties available in the lobby if not all properties are needed to pick a room.
- void [ClearExpectedUsers](#) ()
Attempts to remove all current expected users from the server's Slot Reservation list.
- override string [ToString](#) ()
Returns a summary of this [Room](#) instance as string.
- new string [ToStringFull](#) ()
Returns a summary of this [Room](#) instance as longer string, including Custom Properties.

Properties

- new string [Name](#) [get, set]
The name of a room. Unique identifier (per Loadbalancing group) for a room/match.
- new bool [IsOpen](#) [get, set]
Defines if the room can be joined. This does not affect listing in a lobby but joining the room will fail if not open. If not open, the room is excluded from random matchmaking. Due to racing conditions, found matches might become closed before they are joined. Simply re-connect to master and find another. Use property "visible" to not list the room.
- new bool [IsVisible](#) [get, set]
Defines if the room is listed in its lobby. Rooms can be created invisible, or changed to invisible. To change if a room can be joined, use property: open.
- string[] [PropertiesListedInLobby](#) [get, set]
A list of custom properties that should be forwarded to the lobby and listed there.
- bool [AutoCleanUp](#) [get]
Gets if this room uses autoCleanUp to remove all (buffered) RPCs and instantiated GameObjects when a player leaves.
- new int [MaxPlayers](#) [get, set]
Sets a limit of players to this room. This property is shown in lobby, too. If the room is full (players count == maxplayers), joining this room will fail.

- new int `PlayerCount` [get]
Count of players in this room.
- string[] `ExpectedUsers` [get]
List of users who are expected to join this room. In matchmaking, `Photon` blocks a slot for each of these UserIDs out of the `MaxPlayers`.
- new string `name` [get, set]
- new bool `open` [get, set]
- new bool `visible` [get, set]
- string[] `propertiesListedInLobby` [get, set]
- bool `autoCleanUp` [get]
- new int `maxPlayers` [get, set]
- new int `playerCount` [get]
- string[] `expectedUsers` [get]

Additional Inherited Members

8.53.1 Detailed Description

This class resembles a room that PUN joins (or joined). The properties are settable as opposed to those of a `RoomInfo` and you can close or hide "your" room.

8.53.2 Member Function Documentation

8.53.2.1 void Room.ClearExpectedUsers ()

Attempts to remove all current expected users from the server's Slot Reservation list.

Note that this operation can conflict with new/other users joining. They might be adding users to the list of expected users before or after this client called `ClearExpectedUsers`.

This room's `expectedUsers` value will update, when the server sends a successful update.

Internals: This methods wraps up setting the `ExpectedUsers` property of a room.

8.53.2.2 void Room.SetCustomProperties (Hashtable propertiesToSet, Hashtable expectedValues = null, bool webForward = false)

Updates the current room's Custom Properties with new/updated key-values.

Custom Properties are a key-value set (Hashtable) which is available to all players in a room. They can relate to the room or individual players and are useful when only the current value of something is of interest. For example: The map of a room. All keys must be strings.

The `Room` and the `PhotonPlayer` class both have `SetCustomProperties` methods. Also, both classes offer access to current key-values by: `customProperties`.

Always use `SetCustomProperties` to change values. To reduce network traffic, set only values that actually changed. New properties are added, existing values are updated. Other values will not be changed, so only provide values that changed or are new.

To delete a named (custom) property of this room, use null as value.

Locally, `SetCustomProperties` will update it's cache without delay. Other clients are updated through `Photon` (the server) with a fitting operation.

Check and Swap

`SetCustomProperties` have the option to do a server-side Check-And-Swap (CAS): Values only get updated if the expected values are correct. The `expectedValues` can be different key/values than the `propertiesToSet`. So you can check some key and set another key's value (if the check succeeds).

If the client's knowledge of properties is wrong or outdated, it can't set values with CAS. This can be useful to keep players from concurrently setting values. For example: If all players try to pickup some card or item, only one should get it. With CAS, only the first SetProperties gets executed server-side and any other (sent at the same time) fails.

The server will broadcast successfully changed values and the local "cache" of customProperties only gets updated after a roundtrip (if anything changed).

You can do a "webForward": [Photon](#) will send the changed properties to a WebHook defined for your application.

OfflineMode

While [PhotonNetwork.offlineMode](#) is true, the expectedValues and webForward parameters are ignored. In Offline↔ Mode, the local customProperties values are immediately updated (without the roundtrip).

Parameters

<i>propertiesToSet</i>	The new properties to be set.
<i>expectedValues</i>	At least one property key/value set to check server-side. Key and value must be correct. Ignored in OfflineMode.
<i>webForward</i>	Set to true, to forward the set properties to a WebHook, defined for this app (in Dashboard). Ignored in OfflineMode.

8.53.2.3 void Room.SetPropertiesListedInLobby (string[] propsListedInLobby)

Enables you to define the properties available in the lobby if not all properties are needed to pick a room.

It makes sense to limit the amount of properties sent to users in the lobby as this improves speed and stability.

Parameters

<i>propsListedIn↔ Lobby</i>	An array of custom room property names to forward to the lobby.
---------------------------------	---

8.53.2.4 override string Room.ToString ()

Returns a summary of this [Room](#) instance as string.

Returns

Summary of this [Room](#) instance.

8.53.2.5 new string Room.ToStringFull ()

Returns a summary of this [Room](#) instance as longer string, including Custom Properties.

Returns

Summary of this [Room](#) instance.

8.53.3 Property Documentation

8.53.3.1 bool Room.AutoCleanUp [get]

Gets if this room uses autoCleanUp to remove all (buffered) RPCs and instantiated GameObjects when a player leaves.

8.53.3.2 **bool** Room.autoCleanUp [get]

8.53.3.3 **string []** Room.ExpectedUsers [get]

List of users who are expected to join this room. In matchmaking, [Photon](#) blocks a slot for each of these UserIDs out of the MaxPlayers.

The corresponding feature in [Photon](#) is called "Slot Reservation" and can be found in the doc pages. Define expected players in the [PhotonNetwork](#) methods: CreateRoom, JoinRoom and JoinOrCreateRoom.

8.53.3.4 **string []** Room.expectedUsers [get]

8.53.3.5 **new bool** Room.IsOpen [get], [set]

Defines if the room can be joined. This does not affect listing in a lobby but joining the room will fail if not open. If not open, the room is excluded from random matchmaking. Due to racing conditions, found matches might become closed before they are joined. Simply re-connect to master and find another. Use property "visible" to not list the room.

8.53.3.6 **new bool** Room.IsVisible [get], [set]

Defines if the room is listed in its lobby. Rooms can be created invisible, or changed to invisible. To change if a room can be joined, use property: open.

8.53.3.7 **new int** Room.MaxPlayers [get], [set]

Sets a limit of players to this room. This property is shown in lobby, too. If the room is full (players count == maxplayers), joining this room will fail.

8.53.3.8 **new int** Room.maxPlayers [get], [set]

8.53.3.9 **new string** Room.Name [get], [set]

The name of a room. Unique identifier (per Loadbalancing group) for a room/match.

8.53.3.10 **new string** Room.name [get], [set]

8.53.3.11 **new bool** Room.open [get], [set]

8.53.3.12 **new int** Room.PlayerCount [get]

Count of players in this room.

8.53.3.13 **new int** Room.playerCount [get]

8.53.3.14 **string []** Room.PropertiesListedInLobby [get], [set]

A list of custom properties that should be forwarded to the lobby and listed there.

8.53.3.15 **string []** Room.propertiesListedInLobby [get], [set]

8.53.3.16 **new bool** Room.visible [get], [set]

8.54 RoomInfo Class Reference

A simplified room with just the info required to list and join, used for the room listing in the lobby. The properties are not settable (open, MaxPlayers, etc).

Inherited by [Room](#).

Public Member Functions

- override bool [Equals](#) (object other)
Makes [RoomInfo](#) comparable (by name).
- override int [GetHashCode](#) ()
Accompanies Equals, using the name's GetHashCode as return.
- override string [ToString](#) ()
Simple printingin method.
- string [ToStringFull](#) ()
Simple printingin method.

Protected Attributes

- byte [maxPlayersField](#) = 0
Backing field for property.
- string[] [expectedUsersField](#)
Backing field for property.
- bool [openField](#) = true
Backing field for property.
- bool [visibleField](#) = true
Backing field for property.
- bool [autoCleanUpField](#) = [PhotonNetwork.autoCleanUpPlayerObjects](#)
Backing field for property. False unless the GameProperty is set to true (else it's not sent).
- string [nameField](#)
Backing field for property.

Properties

- bool [removedFromList](#) [get, set]
Used internally in lobby, to mark rooms that are no longer listed.
- [Hashtable CustomProperties](#) [get]
Read-only "cache" of custom properties of a room. Set via [Room.SetCustomProperties](#) (not available for [RoomInfo](#) class!).
- string [Name](#) [get]
The name of a room. Unique identifier (per Loadbalancing group) for a room/match.
- int [PlayerCount](#) [get, set]
Only used internally in lobby, to display number of players in room (while you're not in).
- bool [IsLocalClientInside](#) [get, set]
State if the local client is already in the game or still going to join it on gameserver (in lobby always false).
- byte [MaxPlayers](#) [get]
Sets a limit of players to this room. This property is shown in lobby, too. If the room is full (players count == maxplayers), joining this room will fail.
- bool [IsOpen](#) [get]

Defines if the room can be joined. This does not affect listing in a lobby but joining the room will fail if not open. If not open, the room is excluded from random matchmaking. Due to racing conditions, found matches might become closed before they are joined. Simply re-connect to master and find another. Use property "IsVisible" to not list the room.

- bool [IsVisible](#) [get]

Defines if the room is listed in its lobby. Rooms can be created invisible, or changed to invisible. To change if a room can be joined, use property: open.

- [Hashtable](#) [customProperties](#) [get]
- string [name](#) [get]
- int [playerCount](#) [get, set]
- bool [isLocalClientInside](#) [get, set]
- byte [maxPlayers](#) [get]
- bool [open](#) [get]
- bool [visible](#) [get]

8.54.1 Detailed Description

A simplified room with just the info required to list and join, used for the room listing in the lobby. The properties are not settable (open, MaxPlayers, etc).

This class resembles info about available rooms, as sent by the Master server's lobby. Consider all values as readonly. None are synced (only updated by events by server).

8.54.2 Member Function Documentation

8.54.2.1 override bool RoomInfo.Equals (object *other*)

Makes [RoomInfo](#) comparable (by name).

8.54.2.2 override int RoomInfo.GetHashCode ()

Accompanies Equals, using the name's Hashcode as return.

Returns

8.54.2.3 override string RoomInfo.ToString ()

Simple printingin method.

Returns

Summary of this [RoomInfo](#) instance.

8.54.2.4 string RoomInfo.ToStringFull ()

Simple printingin method.

Returns

Summary of this [RoomInfo](#) instance.

8.54.3 Member Data Documentation

8.54.3.1 `bool RoomInfo.autoCleanUpField = PhotonNetwork.autoCleanUpPlayerObjects` [protected]

Backing field for property. False unless the `GameProperty` is set to true (else it's not sent).

8.54.3.2 `string [] RoomInfo.expectedUsersField` [protected]

Backing field for property.

8.54.3.3 `byte RoomInfo.maxPlayersField = 0` [protected]

Backing field for property.

8.54.3.4 `string RoomInfo.nameField` [protected]

Backing field for property.

8.54.3.5 `bool RoomInfo.openField = true` [protected]

Backing field for property.

8.54.3.6 `bool RoomInfo.visibleField = true` [protected]

Backing field for property.

8.54.4 Property Documentation

8.54.4.1 `Hashtable RoomInfo.CustomProperties` [get]

Read-only "cache" of custom properties of a room. Set via [Room.SetCustomProperties](#) (not available for [RoomInfo](#) class!).

All keys are string-typed and the values depend on the game/application.

[Room.SetCustomProperties](#)

8.54.4.2 `Hashtable RoomInfo.customProperties` [get]

8.54.4.3 `bool RoomInfo.IsLocalClientInside` [get], [set]

State if the local client is already in the game or still going to join it on gameserver (in lobby always false).

8.54.4.4 `bool RoomInfo.isLocalClientInside` [get], [set]

8.54.4.5 `bool RoomInfo.IsOpen` [get]

Defines if the room can be joined. This does not affect listing in a lobby but joining the room will fail if not open. If not open, the room is excluded from random matchmaking. Due to racing conditions, found matches might become closed before they are joined. Simply re-connect to master and find another. Use property "IsVisible" to not list the room.

As part of [RoomInfo](#) this can't be set. As part of a [Room](#) (which the player joined), the setter will update the server and all clients.

8.54.4.6 bool RoomInfo.IsVisible [get]

Defines if the room is listed in its lobby. Rooms can be created invisible, or changed to invisible. To change if a room can be joined, use property: open.

As part of [RoomInfo](#) this can't be set. As part of a [Room](#) (which the player joined), the setter will update the server and all clients.

8.54.4.7 byte RoomInfo.MaxPlayers [get]

Sets a limit of players to this room. This property is shown in lobby, too. If the room is full (players count == maxplayers), joining this room will fail.

As part of [RoomInfo](#) this can't be set. As part of a [Room](#) (which the player joined), the setter will update the server and all clients.

8.54.4.8 byte RoomInfo.maxPlayers [get]

8.54.4.9 string RoomInfo.Name [get]

The name of a room. Unique identifier (per Loadbalancing group) for a room/match.

8.54.4.10 string RoomInfo.name [get]

8.54.4.11 bool RoomInfo.open [get]

8.54.4.12 int RoomInfo.PlayerCount [get], [set]

Only used internally in lobby, to display number of players in room (while you're not in).

8.54.4.13 int RoomInfo.playerCount [get], [set]

8.54.4.14 bool RoomInfo.removedFromList [get], [set]

Used internally in lobby, to mark rooms that are no longer listed.

8.54.4.15 bool RoomInfo.visible [get]

8.55 RoomOptions Class Reference

Wraps up common room properties needed when you create rooms. Read the individual entries for more details.

Public Attributes

- byte [MaxPlayers](#)

Max number of players that can be in the room at any time. 0 means "no limit".

- int [PlayerTtl](#)

Time To Live (TTL) for an 'actor' in a room. If a client disconnects, this actor is inactive first and removed after this timeout. In milliseconds.

- int [EmptyRoomTtl](#)
Time To Live (TTL) for a room when the last player leaves. Keeps room in memory for case a player re-joins soon. In milliseconds.
- [Hashtable CustomRoomProperties](#)
The room's custom properties to set. Use string keys!
- string[] [CustomRoomPropertiesForLobby](#) = new string[0]
Defines the custom room properties that get listed in the lobby.
- string[] [Plugins](#)
Informs the server of the expected plugin setup.

Properties

- bool [IsVisible](#) [get, set]
Defines if this room is listed in the lobby. If not, it also is not joined randomly.
- bool [IsOpen](#) [get, set]
Defines if this room can be joined at all.
- bool [CleanupCacheOnLeave](#) [get, set]
Removes a user's events and properties from the room when a user leaves.
- bool [SuppressRoomEvents](#) [get]
Tells the server to skip room events for joining and leaving players.
- bool [PublishUserId](#) [get, set]
Defines if the UserIds of players get "published" in the room. Useful for FindFriends, if players want to play another game together.
- bool [DeleteNullProperties](#) [get, set]
Optionally, properties get deleted, when null gets assigned as value. Defaults to off / false.
- bool [isVisible](#) [get, set]
- bool [isOpen](#) [get, set]
- byte [maxPlayers](#) [get, set]
- bool [cleanupCacheOnLeave](#) [get, set]
- [Hashtable customRoomProperties](#) [get, set]
- string[] [customRoomPropertiesForLobby](#) [get, set]
- string[] [plugins](#) [get, set]
- bool [suppressRoomEvents](#) [get]
- bool [publishUserId](#) [get, set]

8.55.1 Detailed Description

Wraps up common room properties needed when you create rooms. Read the individual entries for more details.

This directly maps to the fields in the [Room](#) class.

8.55.2 Member Data Documentation

8.55.2.1 Hashtable RoomOptions.CustomRoomProperties

The room's custom properties to set. Use string keys!

Custom room properties are any key-values you need to define the game's setup. The shorter your keys are, the better. Example: Map, Mode (could be "m" when used with "Map"), TileSet (could be "t").

8.55.2.2 `string [] RoomOptions.CustomRoomPropertiesForLobby = new string[0]`

Defines the custom room properties that get listed in the lobby.

Name the custom room properties that should be available to clients that are in a lobby. Use with care. Unless a custom property is essential for matchmaking or user info, it should not be sent to the lobby, which causes traffic and delays for clients in the lobby.

Default: No custom properties are sent to the lobby.

8.55.2.3 `int RoomOptions.EmptyRoomTtl`

Time To Live (TTL) for a room when the last player leaves. Keeps room in memory for case a player re-joins soon. In milliseconds.

8.55.2.4 `byte RoomOptions.MaxPlayers`

Max number of players that can be in the room at any time. 0 means "no limit".

8.55.2.5 `int RoomOptions.PlayerTtl`

Time To Live (TTL) for an 'actor' in a room. If a client disconnects, this actor is inactive first and removed after this timeout. In milliseconds.

8.55.2.6 `string [] RoomOptions.Plugins`

Informs the server of the expected plugin setup.

The operation will fail in case of a plugin mismatch returning error code `PluginMismatch 32757(0x7FFF - 10)`. Setting `string[]{}` means the client expects no plugin to be setup. Note: for backwards compatibility null omits any check.

8.55.3 Property Documentation**8.55.3.1** `bool RoomOptions.CleanupCacheOnLeave` `[get]`, `[set]`

Removes a user's events and properties from the room when a user leaves.

This makes sense when in rooms where players can't place items in the room and just vanish entirely. When you disable this, the event history can become too long to load if the room stays in use indefinitely. Default: true. Cleans up the cache and props of leaving users.

8.55.3.2 `bool RoomOptions.cleanupCacheOnLeave` `[get]`, `[set]`**8.55.3.3** `Hashtable RoomOptions.customRoomProperties` `[get]`, `[set]`**8.55.3.4** `string [] RoomOptions.customRoomPropertiesForLobby` `[get]`, `[set]`**8.55.3.5** `bool RoomOptions.DeleteNullProperties` `[get]`, `[set]`

Optionally, properties get deleted, when null gets assigned as value. Defaults to off / false.

When `Op SetProperties` is setting a key's value to null, the server and clients should remove the key/value from the Custom Properties. By default, the server keeps the keys (and null values) and sends them to joining players.

Important: Only when `SetProperties` does a "broadcast", the change (key, value = null) is sent to clients to update accordingly. This applies to Custom Properties for rooms and actors/players.

8.55.3.6 bool RoomOptions.IsOpen [get], [set]

Defines if this room can be joined at all.

If a room is closed, no player can join this. As example this makes sense when 3 of 4 possible players start their gameplay early and don't want anyone to join during the game. The room can still be listed in the lobby (set `IsVisible` to control lobby-visibility).

8.55.3.7 bool RoomOptions.isOpen [get], [set]**8.55.3.8 bool RoomOptions.IsVisible** [get], [set]

Defines if this room is listed in the lobby. If not, it also is not joined randomly.

A room that is not visible will be excluded from the room lists that are sent to the clients in lobbies. An invisible room can be joined by name but is excluded from random matchmaking.

Use this to "hide" a room and simulate "private rooms". Players can exchange a roomname and create it invisible to avoid anyone else joining it.

8.55.3.9 bool RoomOptions.isVisible [get], [set]**8.55.3.10 byte RoomOptions.maxPlayers** [get], [set]**8.55.3.11 string [] RoomOptions.plugins** [get], [set]**8.55.3.12 bool RoomOptions.PublishUserId** [get], [set]

Defines if the UserIds of players get "published" in the room. Useful for FindFriends, if players want to play another game together.

When you set this to true, [Photon](#) will publish the UserIds of the players in that room. In that case, you can use [PhotonPlayer.UserId](#), to access any player's userID. This is useful for FindFriends and to set "expected users" to reserve slots in a room (see [PhotonNetwork.JoinRoom](#) e.g.).

8.55.3.13 bool RoomOptions.publishUserId [get], [set]**8.55.3.14 bool RoomOptions.SuppressRoomEvents** [get]

Tells the server to skip room events for joining and leaving players.

Using this makes the client unaware of the other players in a room. That can save some traffic if you have some server logic that updates players but it can also limit the client's usability.

PUN will break if you use this, so it's not settable.

8.55.3.15 bool RoomOptions.suppressRoomEvents [get]

8.56 UnityEngine.SceneManagement.SceneManager Class Reference

Minimal implementation of the [SceneManager](#) for older Unity, up to v5.2.

Static Public Member Functions

- static void [LoadScene](#) (string name)
- static void [LoadScene](#) (int buildIndex)

8.56.1 Detailed Description

Minimal implementation of the [SceneManager](#) for older Unity, up to v5.2.

8.56.2 Member Function Documentation

8.56.2.1 static void [UnityEngine.SceneManagement.SceneManager.LoadScene](#) (string *name*) [static]

8.56.2.2 static void [UnityEngine.SceneManagement.SceneManager.LoadScene](#) (int *buildIndex*) [static]

8.57 SceneManagerHelper Class Reference

Properties

- static string [ActiveSceneName](#) [get]
- static int [ActiveSceneBuildIndex](#) [get]

8.57.1 Property Documentation

8.57.1.1 int [SceneManagerHelper.ActiveSceneBuildIndex](#) [static], [get]

8.57.1.2 string [SceneManagerHelper.ActiveSceneName](#) [static], [get]

8.58 ServerSettings Class Reference

Collection of connection-relevant settings, used internally by [PhotonNetwork.ConnectUsingSettings](#).

Inherits [ScriptableObject](#).

Public Types

- enum [HostingOption](#) {
[HostingOption.NotSet](#) = 0, [HostingOption.PhotonCloud](#) = 1, [HostingOption.SelfHosted](#) = 2, [HostingOption.OfflineMode](#) = 3,
[HostingOption.BestRegion](#) = 4 }

Public Member Functions

- void [UseCloudBestRegion](#) (string cloudAppid)
- void [UseCloud](#) (string cloudAppid)
- void [UseCloud](#) (string cloudAppid, [CloudRegionCode](#) code)
- void [UseMyServer](#) (string serverAddress, int serverPort, string application)
- override string [ToString](#) ()

Static Public Member Functions

- static bool [IsAppId](#) (string val)
Checks if a string is a Guid by attempting to create one.
- static void [ResetBestRegionCodeInPreferences](#) ()

Public Attributes

- string [AppID](#) = ""
- string [VoiceAppID](#) = ""
- string [ChatAppID](#) = ""
- [HostingOption](#) [HostType](#) = [HostingOption.NotSet](#)
- [CloudRegionCode](#) [PreferredRegion](#)
- [CloudRegionFlag](#) [EnabledRegions](#) = ([CloudRegionFlag](#))(-1)
- [ConnectionProtocol](#) [Protocol](#) = [ConnectionProtocol.Udp](#)
- string [ServerAddress](#) = ""
- int [ServerPort](#) = 5055
- int [VoiceServerPort](#) = 5055
- bool [JoinLobby](#)
- bool [EnableLobbyStatistics](#)
- [PhotonLogLevel](#) [PunLogging](#) = [PhotonLogLevel.ErrorsOnly](#)
- [DebugLevel](#) [NetworkLogging](#) = [DebugLevel.ERROR](#)
- bool [RunInBackground](#) = true
- List< string > [RpcList](#) = new List<string>()
- bool [DisableAutoOpenWizard](#)

Properties

- static [CloudRegionCode](#) [BestRegionCodeInPreferences](#) [get]
Gets the best region code in preferences. This composes the PhotonHandler, since its Internal and can not be accessed by the custom inspector

8.58.1 Detailed Description

Collection of connection-relevant settings, used internally by [PhotonNetwork.ConnectUsingSettings](#).

8.58.2 Member Enumeration Documentation

8.58.2.1 enum [ServerSettings.HostingOption](#)

Enumerator

NotSet
PhotonCloud
SelfHosted
OfflineMode
BestRegion

8.58.3 Member Function Documentation

8.58.3.1 static bool [ServerSettings.IsAppId](#) (string val) [static]

Checks if a string is a Guid by attempting to create one.

Parameters

<i>val</i>	The potential guid to check.
------------	------------------------------

Returns

True if new Guid(*val*) did not fail.

8.58.3.2 `static void ServerSettings.ResetBestRegionCodeInPreferences () [static]`

8.58.3.3 `override string ServerSettings.ToString ()`

8.58.3.4 `void ServerSettings.UseCloud (string cloudAppid)`

8.58.3.5 `void ServerSettings.UseCloud (string cloudAppid, CloudRegionCode code)`

8.58.3.6 `void ServerSettings.UseCloudBestRegion (string cloudAppid)`

8.58.3.7 `void ServerSettings.UseMyServer (string serverAddress, int serverPort, string application)`

8.58.4 Member Data Documentation

8.58.4.1 `string ServerSettings.AppID = ""`

8.58.4.2 `string ServerSettings.ChatAppID = ""`

8.58.4.3 `bool ServerSettings.DisableAutoOpenWizard`

8.58.4.4 `CloudRegionFlag ServerSettings.EnabledRegions = (CloudRegionFlag)(-1)`

8.58.4.5 `bool ServerSettings.EnableLobbyStatistics`

8.58.4.6 `HostingOption ServerSettings.HostType = HostingOption.NotSet`

8.58.4.7 `bool ServerSettings.JoinLobby`

8.58.4.8 `DebugLevel ServerSettings.NetworkLogging = DebugLevel.ERROR`

8.58.4.9 `CloudRegionCode ServerSettings.PreferredRegion`

8.58.4.10 `ConnectionProtocol ServerSettings.Protocol = ConnectionProtocol.Udp`

8.58.4.11 `PhotonLogLevel ServerSettings.PunLogging = PhotonLogLevel.ErrorsOnly`

8.58.4.12 `List<string> ServerSettings.RpcList = new List<string>()`

8.58.4.13 `bool ServerSettings.RunInBackground = true`

8.58.4.14 `string ServerSettings.ServerAddress = ""`

8.58.4.15 `int ServerSettings.ServerPort = 5055`

8.58.4.16 `string ServerSettings.VoiceAppID = ""`

8.58.4.17 `int ServerSettings.VoiceServerPort = 5055`

8.58.5 Property Documentation

8.58.5.1 `CloudRegionCode` `ServerSettings.BestRegionCodeInPreferences` `[static]`, `[get]`

Gets the best region code in preferences. This composes the `PhotonHandler`, since its `Internal` and can not be accessed by the custom inspector

The best region code in preferences.

8.59 `PhotonAnimatorView.SynchronizedLayer` Class Reference

Public Attributes

- [SynchronizeType](#) `SynchronizeType`
- `int` [LayerIndex](#)

8.59.1 Member Data Documentation

8.59.1.1 `int` `PhotonAnimatorView.SynchronizedLayer.LayerIndex`

8.59.1.2 `SynchronizeType` `PhotonAnimatorView.SynchronizedLayer.SynchronizeType`

8.60 `PhotonAnimatorView.SynchronizedParameter` Class Reference

Public Attributes

- `ParameterType` `Type`
- [SynchronizeType](#) `SynchronizeType`
- `string` [Name](#)

8.60.1 Member Data Documentation

8.60.1.1 `string` `PhotonAnimatorView.SynchronizedParameter.Name`

8.60.1.2 `SynchronizeType` `PhotonAnimatorView.SynchronizedParameter.SynchronizeType`

8.60.1.3 `ParameterType` `PhotonAnimatorView.SynchronizedParameter.Type`

8.61 `TypedLobby` Class Reference

Refers to a specific lobby (and type) on the server.

Inherited by [TypedLobbyInfo](#).

Public Member Functions

- [TypedLobby](#) ()
- [TypedLobby](#) (`string` name, [LobbyType](#) type)
- override `string` [ToString](#) ()

Public Attributes

- string [Name](#)
Name of the lobby this game gets added to. Default: null, attached to default lobby. Lobbies are unique per lobbyName plus lobbyType, so the same name can be used when several types are existing.
- [LobbyType](#) Type
Type of the (named)lobby this game gets added to

Static Public Attributes

- static readonly [TypedLobby](#) [Default](#) = new [TypedLobby](#)()

Properties

- bool [IsDefault](#) [get]

8.61.1 Detailed Description

Refers to a specific lobby (and type) on the server.

The name and type are the unique identifier for a lobby.

Join a lobby via [PhotonNetwork.JoinLobby\(TypedLobby lobby\)](#).

The current lobby is stored in [PhotonNetwork.lobby](#).

8.61.2 Constructor & Destructor Documentation

8.61.2.1 [TypedLobby.TypedLobby \(\)](#)

8.61.2.2 [TypedLobby.TypedLobby \(string name, LobbyType type \)](#)

8.61.3 Member Function Documentation

8.61.3.1 override string [TypedLobby.ToString \(\)](#)

8.61.4 Member Data Documentation

8.61.4.1 readonly [TypedLobby](#) [TypedLobby.Default](#) = new [TypedLobby](#)() [static]

8.61.4.2 string [TypedLobby.Name](#)

Name of the lobby this game gets added to. Default: null, attached to default lobby. Lobbies are unique per lobbyName plus lobbyType, so the same name can be used when several types are existing.

8.61.4.3 [LobbyType](#) [TypedLobby.Type](#)

Type of the (named)lobby this game gets added to

8.61.5 Property Documentation

8.61.5.1 bool [TypedLobby.IsDefault](#) [get]

8.62 TypedLobbyInfo Class Reference

Inherits [TypedLobby](#).

Public Member Functions

- override string [ToString](#) ()

Public Attributes

- int [PlayerCount](#)
- int [RoomCount](#)

Additional Inherited Members

8.62.1 Member Function Documentation

8.62.1.1 override string TypedLobbyInfo.ToString ()

8.62.2 Member Data Documentation

8.62.2.1 int TypedLobbyInfo.PlayerCount

8.62.2.2 int TypedLobbyInfo.RoomCount

8.63 WebRpcResponse Class Reference

Reads an operation response of a WebRpc and provides convenient access to most common values.

Public Member Functions

- [WebRpcResponse](#) (OperationResponse response)
An OperationResponse for a WebRpc is needed to read it's values.
- string [ToStringFull](#) ()
Turns the response into an easier to read string.

Properties

- string [Name](#) [get, set]
Name of the WebRpc that was called.
- int [ReturnCode](#) [get, set]
ReturnCode of the WebService that answered the WebRpc.
- string [DebugMessage](#) [get, set]
Might be empty or null.
- Dictionary< string, object > [Parameters](#) [get, set]
Other key/values returned by the webservice that answered the WebRpc.

8.63.1 Detailed Description

Reads an operation response of a WebRpc and provides convenient access to most common values.

See method [PhotonNetwork.WebRpc](#).

Create a [WebRpcResponse](#) to access common result values.

The operationResponse.OperationCode should be: [OperationCode.WebRpc](#).

8.63.2 Constructor & Destructor Documentation

8.63.2.1 WebRpcResponse.WebRpcResponse (OperationResponse *response*)

An OperationResponse for a WebRpc is needed to read it's values.

8.63.3 Member Function Documentation

8.63.3.1 string WebRpcResponse.ToStringFull ()

Turns the response into an easier to read string.

Returns

String resembling the result.

8.63.4 Property Documentation

8.63.4.1 string WebRpcResponse.DebugMessage [get], [set]

Might be empty or null.

8.63.4.2 string WebRpcResponse.Name [get], [set]

Name of the WebRpc that was called.

8.63.4.3 Dictionary<string, object> WebRpcResponse.Parameters [get], [set]

Other key/values returned by the webservice that answered the WebRpc.

8.63.4.4 int WebRpcResponse.ReturnCode [get], [set]

ReturnCode of the WebService that answered the WebRpc.

0 is commonly used to signal success.

-1 tells you: Got no ReturnCode from WebRpc service.

Other ReturnCodes are defined by the individual WebRpc and service.

Chapter 9

File Documentation

- 9.1 C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking/Assets/_Doc/general.md File Reference
- 9.2 C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking/Assets/_Doc/main.md File Reference
- 9.3 C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking/Assets/_Doc/optionalGui.md File Reference
- 9.4 C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking/Assets/_Doc/photonStatsGui.md File Reference
- 9.5 C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking/Assets/_Doc/publicApi.md File Reference
- 9.6 C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking/Assets/Photon Unity Networking/Plugins/PhotonNetwork/CustomTypes.cs File Reference

Sets up support for Unity-specific types. Can be a blueprint how to register your own Custom Types for sending.

Classes

- class **CustomTypes**

Internally used class, containing de/serialization methods for various Unity-specific classes. Adding those to the [Photon](#) serialization protocol allows you to send them in events, etc.

9.6.1 Detailed Description

Sets up support for Unity-specific types. Can be a blueprint how to register your own Custom Types for sending.

9.7 C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking/Assets/Photon Unity Networking/Plugins/PhotonNetwork/Enums.cs File Reference

Wraps up several of the commonly used enumerations.

Classes

- class [EncryptionDataParameters](#)

Enumerations

- enum [PhotonNetworkingMessage](#) {
[PhotonNetworkingMessage.OnConnectedToPhoton](#), [PhotonNetworkingMessage.OnLeftRoom](#), [PhotonNetworkingMessage.OnMasterClientSwitched](#), [PhotonNetworkingMessage.OnPhotonCreateRoomFailed](#),
[PhotonNetworkingMessage.OnPhotonJoinRoomFailed](#), [PhotonNetworkingMessage.OnCreatedRoom](#),
[PhotonNetworkingMessage.OnJoinedLobby](#), [PhotonNetworkingMessage.OnLeftLobby](#),
[PhotonNetworkingMessage.OnDisconnectedFromPhoton](#), [PhotonNetworkingMessage.OnConnectionFail](#),
[PhotonNetworkingMessage.OnFailedToConnectToPhoton](#), [PhotonNetworkingMessage.OnReceivedRoomListUpdate](#),
[PhotonNetworkingMessage.OnJoinedRoom](#), [PhotonNetworkingMessage.OnPhotonPlayerConnected](#),
[PhotonNetworkingMessage.OnPhotonPlayerDisconnected](#), [PhotonNetworkingMessage.OnPhotonRandomJoinFailed](#),
[PhotonNetworkingMessage.OnConnectedToMaster](#), [PhotonNetworkingMessage.OnPhotonSerializeView](#),
[PhotonNetworkingMessage.OnPhotonInstantiate](#), [PhotonNetworkingMessage.OnPhotonMaxCcuReached](#),
[PhotonNetworkingMessage.OnPhotonCustomRoomPropertiesChanged](#), [PhotonNetworkingMessage.OnPhotonPlayerPropertiesChanged](#), [PhotonNetworkingMessage.OnUpdatedFriendList](#), [PhotonNetworkingMessage.OnCustomAuthenticationFailed](#),
[PhotonNetworkingMessage.OnCustomAuthenticationResponse](#), [PhotonNetworkingMessage.OnWebRpcResponse](#), [PhotonNetworkingMessage.OnOwnershipRequest](#), [PhotonNetworkingMessage.OnLobbyStatisticsUpdate](#),
[PhotonNetworkingMessage.OnPhotonPlayerActivityChanged](#), [PhotonNetworkingMessage.OnOwnershipTransferred](#) }

This enum defines the set of MonoMessages [Photon Unity Networking](#) is using as callbacks. Implemented by [PhotonBehaviour](#).

- enum [PhotonLogLevel](#) { [PhotonLogLevel.ErrorsOnly](#), [PhotonLogLevel.Informational](#), [PhotonLogLevel.Full](#) }

Used to define the level of logging output created by the PUN classes. Either log errors, info (some more) or full.

- enum [PhotonTargets](#) {
[PhotonTargets.All](#), [PhotonTargets.Others](#), [PhotonTargets.MasterClient](#), [PhotonTargets.AllBuffered](#),
[PhotonTargets.OthersBuffered](#), [PhotonTargets.AllViaServer](#), [PhotonTargets.AllBufferedViaServer](#) }

Enum of "target" options for RPCs. These define which remote clients get your RPC call.

- enum [CloudRegionCode](#) {
[CloudRegionCode.eu](#) = 0, [CloudRegionCode.us](#) = 1, [CloudRegionCode.asia](#) = 2, [CloudRegionCode.jp](#) = 3,
[CloudRegionCode.au](#) = 5, [CloudRegionCode.usw](#) = 6, [CloudRegionCode.sa](#) = 7, [CloudRegionCode.cae](#) = 8,
[CloudRegionCode.kr](#) = 9, [CloudRegionCode.in](#) = 10, [CloudRegionCode.none](#) = 4 }

Currently available [Photon Cloud regions](#) as enum.

- enum [CloudRegionFlag](#) {
[CloudRegionFlag.eu](#) = 1 << 0, [CloudRegionFlag.us](#) = 1 << 1, [CloudRegionFlag.asia](#) = 1 << 2, [CloudRegionFlag.jp](#) = 1 << 3,
[CloudRegionFlag.au](#) = 1 << 4, [CloudRegionFlag.usw](#) = 1 << 5, [CloudRegionFlag.sa](#) = 1 << 6, [CloudRegionFlag.cae](#) = 1 << 7,
[CloudRegionFlag.kr](#) = 1 << 8, [CloudRegionFlag.in](#) = 1 << 9 }

Available regions as enum of flags. To be used as "enabled" flags for Best [Region](#) ping.

- enum [ConnectionState](#) {
[ConnectionState.Disconnected](#), [ConnectionState.Connecting](#), [ConnectionState.Connected](#), [ConnectionState.Disconnecting](#),
[ConnectionState.InitializingApplication](#) }
High level connection state of the client. Better use the more detailed [ClientState](#).
- enum [EncryptionMode](#) { [EncryptionMode.PayloadEncryption](#), [EncryptionMode.DatagramEncryption](#) = 10 }
Defines how the communication gets encrypted.

9.7.1 Detailed Description

Wraps up several of the commonly used enumerations.

9.7.2 Enumeration Type Documentation

9.7.2.1 enum [CloudRegionCode](#)

Currently available [Photon Cloud regions](#) as enum.

This is used in [PhotonNetwork.ConnectToRegion](#).

Enumerator

eu European servers in Amsterdam.
us US servers (East Coast).
asia Asian servers in Singapore.
jp Japanese servers in Tokyo.
au Australian servers in Melbourne.summary>USA West, San José, usw
usw summary>South America, Sao Paulo, sa
sa summary>Canada East, Montreal, cae
cae summary>South Korea, Seoul, kr
kr summary>India, Chennai, in
in
none No region selected.

9.7.2.2 enum [CloudRegionFlag](#)

Available regions as enum of flags. To be used as "enabled" flags for Best [Region](#) ping.

Note that these enum values skip [CloudRegionCode.none](#) and their values are in strict order (power of 2).

Enumerator

eu
us
asia
jp
au
usw
sa
cae
kr
in

9.7.2.3 enum ConnectionState

High level connection state of the client. Better use the more detailed [ClientState](#).

Enumerator

Disconnected
Connecting
Connected
Disconnecting
InitializingApplication

9.7.2.4 enum EncryptionMode

Defines how the communication gets encrypted.

Enumerator

PayloadEncryption This is the default encryption mode: Messages get encrypted only on demand (when you send operations with the "encrypt" parameter set to true).
DatagramEncryption With this encryption mode for UDP, the connection gets setup and all further datagrams get encrypted almost entirely. On-demand message encryption (like in PayloadEncryption) is skipped. This mode requires AuthOnce or AuthOnceWss as AuthMode!

9.8 C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking/Assets/Photon Unity Networking/Plugins/PhotonNetwork/Extensions.cs File Reference

Classes

- class [Extensions](#)
This static class defines some useful extension methods for several existing classes (e.g. Vector3, float and others).
- class [GameObjectExtensions](#)
Small number of extension methods that make it easier for PUN to work cross-Unity-versions.

Typedefs

- using [Hashtable](#) = ExitGames.Client.Photon.Hashtable
- using [SupportClassPun](#) = ExitGames.Client.Photon.SupportClass

9.8.1 Typedef Documentation

9.8.1.1 using [Hashtable](#) = ExitGames.Client.Photon.Hashtable

9.8.1.2 using [SupportClassPun](#) = ExitGames.Client.Photon.SupportClass

9.9 C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking/Assets/Photon Unity Networking/Plugins/PhotonNetwork/FriendInfo.cs File Reference

Classes

- class [FriendInfo](#)
Used to store info about a friend's online state and in which room he/she is.

9.10 C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking/Assets/Photon Unity Networking/Plugins/PhotonNetwork/GizmoType.cs File Reference ↩↩

Classes

- class [ExitGames.Client.GUI.GizmoTypeDrawer](#)

Namespaces

- package [ExitGames.Client.GUI](#)

Enumerations

- enum [ExitGames.Client.GUI.GizmoType](#) { [ExitGames.Client.GUI.GizmoType.WireSphere](#), [ExitGames.Client.GUI.GizmoType.Sphere](#), [ExitGames.Client.GUI.GizmoType.WireCube](#), [ExitGames.Client.GUI.GizmoType.Cube](#) }

9.11 C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking/Assets/Photon Unity Networking/Plugins/PhotonNetwork/LoadbalancingPeer.cs File Reference ↩↩

Classes

- class **LoadBalancingPeer**
A LoadbalancingPeer provides the operations and enum definitions needed to use the loadbalancing server application which is also used in [Photon](#) Cloud.
- class **OpJoinRandomRoomParams**
- class **EnterRoomParams**
- class [ErrorCode](#)
[ErrorCode](#) defines the default codes associated with [Photon](#) client/server communication.
- class [ActorProperties](#)
Class for constants. These (byte) values define "well known" properties for an Actor / Player.
- class [GamePropertyKey](#)
Class for constants. These (byte) values are for "well known" room/game properties used in [Photon](#) Loadbalancing.
- class [EventCode](#)
Class for constants. These values are for events defined by [Photon](#) Loadbalancing.
- class [ParameterCode](#)
Class for constants. Codes for parameters of Operations and Events.
- class [OperationCode](#)
Class for constants. Contains operation codes. Pun uses these constants internally.
- class [RoomOptions](#)
Wraps up common room properties needed when you create rooms. Read the individual entries for more details.
- class [RaiseEventOptions](#)
Aggregates several less-often used options for operation RaiseEvent. See field descriptions for usage details.
- class [TypedLobby](#)
Refers to a specific lobby (and type) on the server.
- class [TypedLobbyInfo](#)
- class [AuthenticationValues](#)
Container for user authentication in [Photon](#). Set AuthValues before you connect - all else is handled.

Enumerations

- enum `JoinMode` : byte { `JoinMode.Default` = 0, `JoinMode.CreateIfNotExists` = 1, `JoinMode.JoinOrRejoin` = 2, `JoinMode.RejoinOnly` = 3 }

Defines possible values for `OpJoinRoom` and `OpJoinOrCreate`. It tells the server if the room can be only be joined normally, created implicitly or found on a web-service for Turnbased games.

- enum `MatchmakingMode` : byte { `MatchmakingMode.FillRoom` = 0, `MatchmakingMode.SerialMatching` = 1, `MatchmakingMode.RandomMatching` = 2 }

Options for matchmaking rules for `OpJoinRandom`.

- enum `ReceiverGroup` : byte { `ReceiverGroup.Others` = 0, `ReceiverGroup.All` = 1, `ReceiverGroup.MasterClient` = 2 }

Lite - `OpRaiseEvent` lets you chose which actors in the room should receive events. By default, events are sent to "Others" but you can overrule this.

- enum `EventCaching` : byte { `EventCaching.DoNotCache` = 0, `EventCaching.MergeCache` = 1, `EventCaching.ReplaceCache` = 2, `EventCaching.RemoveCache` = 3, `EventCaching.AddToRoomCache` = 4, `EventCaching.AddToRoomCacheGlobal` = 5, `EventCaching.RemoveFromRoomCache` = 6, `EventCaching.RemoveFromRoomCacheForActorsLeft` = 7, `EventCaching.SliceIncreaseIndex` = 10, `EventCaching.SliceSetIndex` = 11, `EventCaching.SlicePurgeIndex` = 12, `EventCaching.SlicePurgeUpToIndex` = 13 }

Lite - `OpRaiseEvent` allows you to cache events and automatically send them to joining players in a room. Events are cached per event code and player: Event 100 (example!) can be stored once per player. Cached events can be modified, replaced and removed.

- enum `PropertyTypeFlag` : byte { `PropertyTypeFlag.None` = 0x00, `PropertyTypeFlag.Game` = 0x01, `PropertyTypeFlag.Actor` = 0x02, `PropertyTypeFlag.GameAndActor` = Game | Actor }

Flags for "types of properties", being used as filter in `OpGetProperties`.

- enum `LobbyType` : byte { `LobbyType.Default` = 0, `LobbyType.SqlLobby` = 2, `LobbyType.AsyncRandomLobby` = 3 }

Options of lobby types available. Lobby types might be implemented in certain `Photon` versions and won't be available on older servers.

- enum `AuthModeOption` { `AuthModeOption.Auth`, `AuthModeOption.AuthOnce`, `AuthModeOption.AuthOnceWss` }

Options for authentication modes. From "classic" auth on each server to `AuthOnce` (on `NameServer`).

- enum `CustomAuthenticationType` : byte { `CustomAuthenticationType.Custom` = 0, `CustomAuthenticationType.Steam` = 1, `CustomAuthenticationType.Facebook` = 2, `CustomAuthenticationType.Oculus` = 3, `CustomAuthenticationType.PlayStation` = 4, `CustomAuthenticationType.Xbox` = 5, `CustomAuthenticationType.None` = byte.MaxValue }

Options for optional "Custom Authentication" services used with `Photon`. Used by `OpAuthenticate` after connecting to `Photon`.

9.11.1 Enumeration Type Documentation

9.11.1.1 enum `AuthModeOption`

Options for authentication modes. From "classic" auth on each server to `AuthOnce` (on `NameServer`).

Enumerator

`Auth`

`AuthOnce`

`AuthOnceWss`

9.11.1.2 enum CustomAuthenticationType : byte

Options for optional "Custom Authentication" services used with [Photon](#). Used by OpAuthenticate after connecting to [Photon](#).

Enumerator

Custom Use a custom authentication service. Currently the only implemented option.

Steam Authenticates users by their Steam Account. Set auth values accordingly!

Facebook Authenticates users by their Facebook Account. Set auth values accordingly!

Oculus Authenticates users by their Oculus Account and token.

PlayStation Authenticates users by their PSN Account and token.

Xbox Authenticates users by their Xbox Account and XSTS token.

None Disables custom authentication. Same as not providing any [AuthenticationValues](#) for connect (more precisely for: OpAuthenticate).

9.11.1.3 enum EventCaching : byte

Lite - OpRaiseEvent allows you to cache events and automatically send them to joining players in a room. Events are cached per event code and player: Event 100 (example!) can be stored once per player. Cached events can be modified, replaced and removed.

Caching works only combination with ReceiverGroup options Others and All.

Enumerator

DoNotCache Default value (not sent).

MergeCache Will merge this event's keys with those already cached.

ReplaceCache Replaces the event cache for this eventCode with this event's content.

RemoveCache Removes this event (by eventCode) from the cache.

AddToRoomCache Adds an event to the room's cache

AddToRoomCacheGlobal Adds this event to the cache for actor 0 (becoming a "globally owned" event in the cache).

RemoveFromRoomCache Remove fitting event from the room's cache.

RemoveFromRoomCacheForActorsLeft Removes events of players who already left the room (cleaning up).

SliceIncreaseIndex Increase the index of the sliced cache.

SliceSetIndex Set the index of the sliced cache. You must set RaiseEventOptions.CacheSliceIndex for this.

SlicePurgeIndex Purge cache slice with index. Exactly one slice is removed from cache. You must set RaiseEventOptions.CacheSliceIndex for this.

SlicePurgeUpToIndex Purge cache slices with specified index and anything lower than that. You must set RaiseEventOptions.CacheSliceIndex for this.

9.11.1.4 enum JoinMode : byte

Defines possible values for OpJoinRoom and OpJoinOrCreate. It tells the server if the room can be only be joined normally, created implicitly or found on a web-service for Turnbased games.

These values are not directly used by a game but implicitly set.

Enumerator

Default Regular join. The room must exist.

CreateIfNotExists Join or create the room if it's not existing. Used for OpJoinOrCreate for example.

JoinOrRejoin The room might be out of memory and should be loaded (if possible) from a Turnbased web-service.

RejoinOnly Only re-join will be allowed. If the user is not yet in the room, this will fail.

9.11.1.5 enum LobbyType : byte

Options of lobby types available. Lobby types might be implemented in certain Photon versions and won't be available on older servers.

Enumerator

Default This lobby is used unless another is defined by game or JoinRandom. Room-lists will be sent and JoinRandomRoom can filter by matching properties.

SqlLobby This lobby type lists rooms like Default but JoinRandom has a parameter for SQL-like "where" clauses for filtering. This allows bigger, less, or and and combinations.

AsyncRandomLobby This lobby does not send lists of games. It is only used for OpJoinRandomRoom. It keeps rooms available for a while when there are only inactive users left.

9.11.1.6 enum MatchmakingMode : byte

Options for matchmaking rules for OpJoinRandom.

Enumerator

FillRoom Fills up rooms (oldest first) to get players together as fast as possible. Default. Makes most sense with MaxPlayers > 0 and games that can only start with more players.

SerialMatching Distributes players across available rooms sequentially but takes filter into account. Without filter, rooms get players evenly distributed.

RandomMatching Joins a (fully) random room. Expected properties must match but aside from this, any available room might be selected.

9.11.1.7 enum PropertyTypeFlag : byte

Flags for "types of properties", being used as filter in OpGetProperties.

Enumerator

None (0x00) Flag type for no property type.

Game (0x01) Flag type for game-attached properties.

Actor (0x02) Flag type for actor related properties.

GameAndActor (0x01) Flag type for game AND actor properties. Equal to 'Game'

9.11.1.8 enum ReceiverGroup : byte

Lite - OpRaiseEvent lets you choose which actors in the room should receive events. By default, events are sent to "Others" but you can overrule this.

Enumerator

Others Default value (not sent). Anyone else gets my event.

All Everyone in the current room (including this peer) will get this event.

MasterClient The server sends this event only to the actor with the lowest actorNumber. The "master client" does not have special rights but is the one who is in this room the longest time.

9.12 C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking/Assets/Photon Unity Networking/Plugins/PhotonNetwork/NetworkingPeer.cs File Reference

Classes

- class **NetworkingPeer**

Implements [Photon](#) LoadBalancing used in PUN. This class is used internally by [PhotonNetwork](#) and not intended as public API.

Typedefs

- using [Hashtable](#) = ExitGames.Client.Photon.Hashtable
- using [SupportClassPun](#) = ExitGames.Client.Photon.SupportClass

Enumerations

- enum [ClientState](#) {
[ClientState.Uninitialized](#), [ClientState.PeerCreated](#), [ClientState.Queued](#), [ClientState.Authenticated](#),
[ClientState.JoinedLobby](#), [ClientState.DisconnectingFromMasterserver](#), [ClientState.ConnectingToGameserver](#),
[ClientState.ConnectedToGameserver](#),
[ClientState.Joining](#), [ClientState.Joined](#), [ClientState.Leaving](#), [ClientState.DisconnectingFromGameserver](#),
[ClientState.ConnectingToMasterserver](#), [ClientState.QueuedComingFromGameserver](#), [ClientState.Disconnecting](#), [ClientState.Disconnected](#),
[ClientState.ConnectedToMaster](#), [ClientState.ConnectingToNameServer](#), [ClientState.ConnectedToNameServer](#), [ClientState.DisconnectingFromNameServer](#),
[ClientState.Authenticating](#) }

Detailed connection / networking peer state. PUN implements a loadbalancing and authentication workflow "behind the scenes", so some states will automatically advance to some follow up state. Those states are commented with "(will-change)".

- enum [DisconnectCause](#) {
[DisconnectCause.DisconnectByServerUserLimit](#) = StatusCode.DisconnectByServerUserLimit, [DisconnectCause.ExceptionOnConnect](#) = StatusCode.ExceptionOnConnect, [DisconnectCause.DisconnectByServerTimeout](#) = StatusCode.DisconnectByServer, [DisconnectCause.DisconnectByServerLogic](#) = StatusCode.DisconnectByServerLogic,
[DisconnectCause.Exception](#) = StatusCode.Exception, [DisconnectCause.InvalidAuthentication](#) = ErrorCode.InvalidAuthentication, [DisconnectCause.MaxCcuReached](#) = ErrorCode.MaxCcuReached, [DisconnectCause.InvalidRegion](#) = ErrorCode.InvalidRegion,
[DisconnectCause.SecurityExceptionOnConnect](#) = StatusCode.SecurityExceptionOnConnect, [DisconnectCause.DisconnectByClientTimeout](#) = StatusCode.TimeoutDisconnect, [DisconnectCause.InternalReceiveException](#) = StatusCode.ExceptionOnReceive, [DisconnectCause.AuthenticationTicketExpired](#) = 32753 }

Summarizes the cause for a disconnect. Used in: [OnConnectionFail](#) and [OnFailedToConnectToPhoton](#).

- enum [ServerConnection](#) { [ServerConnection.MasterServer](#), [ServerConnection.GameServer](#), [ServerConnection.NameServer](#) }

Available server (types) for internally used field: server.

9.12.1 Typedef Documentation

9.12.1.1 using [Hashtable](#) = ExitGames.Client.Photon.Hashtable

9.12.1.2 using [SupportClassPun](#) = ExitGames.Client.Photon.SupportClass

9.12.2 Enumeration Type Documentation

9.12.2.1 enum `ServerConnection`

Available server (types) for internally used field: server.

[Photon](#) uses 3 different roles of servers: Name Server, Master Server and Game Server.

Enumerator

MasterServer This server is where matchmaking gets done and where clients can get lists of rooms in lobbies.

GameServer This server handles a number of rooms to execute and relay the messages between players (in a room).

NameServer This server is used initially to get the address (IP) of a Master Server for a specific region. Not used for [Photon](#) OnPremise (self hosted).

9.13 C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking/Assets/Photon Unity Networking/Plugins/PhotonNetwork/PhotonClasses.cs File Reference ↩

Wraps up smaller classes that don't need their own file.

Classes

- interface [IPunObservable](#)
Defines the `OnPhotonSerializeView` method to make it easy to implement correctly for observable scripts.
- interface [IPunCallbacks](#)
This interface is used as definition of all callback methods of PUN, except `OnPhotonSerializeView`. Preferably, implement them individually.
- interface [IPunPrefabPool](#)
Defines all the methods that a Object Pool must implement, so that PUN can use it.
- class [Photon.MonoBehaviour](#)
This class adds the property `photonView`, while logging a warning when your game still uses the `networkView`.
- class [Photon.PunBehaviour](#)
This class provides a `.photonView` and all callbacks/events that PUN can call. Override the events/methods you want to use.
- struct [PhotonMessageInfo](#)
Container class for info about a particular message, RPC or update.
- class **PunEvent**
Defines [Photon](#) event-codes as used by PUN.
- class [PhotonStream](#)
This container is used in `OnPhotonSerializeView()` to either provide incoming data of a [PhotonView](#) or for you to provide it.
- class [HelpURL](#)
Empty implementation of the upcoming [HelpURL](#) of Unity 5.1. This one is only for compatibility of attributes.
- class [UnityEngine.SceneManagement.SceneManager](#)
Minimal implementation of the [SceneManager](#) for older Unity, up to v5.2.
- class [SceneManagerHelper](#)
- class [WebRpcResponse](#)
Reads an operation response of a `WebRpc` and provides convenient access to most common values.

Namespaces

- package [Photon](#)
- package [UnityEngine.SceneManagement](#)

Typedefs

- using [Hashtable](#) = ExitGames.Client.Photon.Hashtable
- using [SupportClassPun](#) = ExitGames.Client.Photon.SupportClass
- using [Photon.Hashtable](#) = ExitGames.Client.Photon.Hashtable

9.13.1 Detailed Description

Wraps up smaller classes that don't need their own file.

9.13.2 Typedef Documentation

9.13.2.1 using [Hashtable](#) = ExitGames.Client.Photon.Hashtable

9.13.2.2 using [SupportClassPun](#) = ExitGames.Client.Photon.SupportClass

9.14 C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking/Assets/Photon Unity Networking/Plugins/PhotonNetwork/PhotonHandler.cs File Reference

Classes

- class **PhotonHandler**
Internal MonoBehaviour that allows [Photon](#) to run an Update loop.

Typedefs

- using [Debug](#) = UnityEngine.Debug
- using [Hashtable](#) = ExitGames.Client.Photon.Hashtable
- using [SupportClassPun](#) = ExitGames.Client.Photon.SupportClass

9.14.1 Typedef Documentation

9.14.1.1 using [Debug](#) = UnityEngine.Debug

9.14.1.2 using [Hashtable](#) = ExitGames.Client.Photon.Hashtable

9.14.1.3 using [SupportClassPun](#) = ExitGames.Client.Photon.SupportClass

9.15 C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking/Assets/Photon Unity Networking/Plugins/PhotonNetwork/PhotonLagSimulationGui.cs File Reference

Part of the [Optional GUI](#).

Classes

- class [PhotonLagSimulationGui](#)
This MonoBehaviour is a basic GUI for the [Photon](#) client's network-simulation feature. It can modify lag (fixed delay), jitter (random lag) and packet loss.

9.15.1 Detailed Description

Part of the [Optional GUI](#).

9.16 C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking/Assets/Photon Unity Networking/Plugins/PhotonNetwork/PhotonNetwork.cs File Reference

Classes

- class [PhotonNetwork](#)

The main class to use the [PhotonNetwork](#) plugin. This class is static.

Typedefs

- using [Debug](#) = UnityEngine.Debug
- using [Hashtable](#) = ExitGames.Client.Photon.Hashtable

9.16.1 Typedef Documentation

9.16.1.1 using [Debug](#) = UnityEngine.Debug

9.16.1.2 using [Hashtable](#) = ExitGames.Client.Photon.Hashtable

9.17 C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking/Assets/Photon Unity Networking/Plugins/PhotonNetwork/PhotonPlayer.cs File Reference

Classes

- class [PhotonPlayer](#)

Summarizes a "player" within a room, identified (in that room) by actorID.

Typedefs

- using [Hashtable](#) = ExitGames.Client.Photon.Hashtable

9.17.1 Typedef Documentation

9.17.1.1 using [Hashtable](#) = ExitGames.Client.Photon.Hashtable

9.18 C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking/Assets/Photon Unity Networking/Plugins/PhotonNetwork/PhotonStatsGui.cs File Reference

Part of the [Optional GUI](#).

Classes

- class [PhotonStatsGui](#)

Basic GUI to show traffic and health statistics of the connection to [Photon](#), toggled by shift+tab.

9.18.1 Detailed Description

Part of the [Optional GUI](#).

9.19 C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking/Assets/Photon Unity Networking/Plugins/PhotonNetwork/PhotonStreamQueue.cs File Reference

Classes

- class [PhotonStreamQueue](#)

The [PhotonStreamQueue](#) helps you poll object states at higher frequencies than what [PhotonNetwork.sendRate](#) dictates and then sends all those states at once when [Serialize\(\)](#) is called. On the receiving end you can call [Deserialize\(\)](#) and then the stream will roll out the received object states in the same order and timeStep they were recorded in.

9.20 C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking/Assets/Photon Unity Networking/Plugins/PhotonNetwork/PhotonView.cs File Reference

Classes

- class [PhotonView](#)

PUN's [NetworkView](#) replacement class for networking. Use it like a [NetworkView](#).

Enumerations

- enum [ViewSynchronization](#) { [ViewSynchronization.Off](#), [ViewSynchronization.ReliableDeltaCompressed](#), [ViewSynchronization.Unreliable](#), [ViewSynchronization.UnreliableOnChange](#) }
- enum [OnSerializeTransform](#) { [OnSerializeTransform.OnlyPosition](#), [OnSerializeTransform.OnlyRotation](#), [OnSerializeTransform.OnlyScale](#), [OnSerializeTransform.PositionAndRotation](#), [OnSerializeTransform.All](#) }
- enum [OnSerializeRigidBody](#) { [OnSerializeRigidBody.OnlyVelocity](#), [OnSerializeRigidBody.OnlyAngularVelocity](#), [OnSerializeRigidBody.All](#) }
- enum [OwnershipOption](#) { [OwnershipOption.Fixed](#), [OwnershipOption.Takeover](#), [OwnershipOption.Request](#) }

Options to define how Ownership Transfer is handled per [PhotonView](#).

9.20.1 Enumeration Type Documentation

9.20.1.1 enum [OnSerializeRigidBody](#)

Enumerator

[OnlyVelocity](#)

[OnlyAngularVelocity](#)

[All](#)

9.20.1.2 enum [OnSerializeTransform](#)

Enumerator

[OnlyPosition](#)

OnlyRotation***OnlyScale******PositionAndRotation******All***

9.20.1.3 enum OwnershipOption

Options to define how Ownership Transfer is handled per [PhotonView](#).

This setting affects how RequestOwnership and TransferOwnership work at runtime.

Enumerator

Fixed Ownership is fixed. Instantiated objects stick with their creator, scene objects always belong to the Master Client.

Takeover Ownership can be taken away from the current owner who can't object.

Request Ownership can be requested with [PhotonView.RequestOwnership](#) but the current owner has to agree to give up ownership. The current owner has to implement [IPunCallbacks.OnOwnershipRequest](#) to react to the ownership request.

9.20.1.4 enum ViewSynchronization

Enumerator

Off***ReliableDeltaCompressed******Unreliable******UnreliableOnChange***

9.21 C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking/Assets/Photon Unity Networking/Plugins/PhotonNetwork/PingCloudRegions.cs File Reference ↩

Classes

- class [PingMonoEditor](#)
Uses C# Socket class from System.Net.Sockets (as Unity usually does).
- class [PhotonPingManager](#)

Typedefs

- using [Debug](#) = UnityEngine.Debug
- using [SupportClassPun](#) = ExitGames.Client.Photon.SupportClass

9.21.1 Typedef Documentation

9.21.1.1 using Debug = UnityEngine.Debug

9.21.1.2 using SupportClassPun = ExitGames.Client.Photon.SupportClass

9.22 C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking/Assets/Photon Unity Networking/Plugins/PhotonNetwork/Room.cs File Reference ↩

Classes

- class [Room](#)

This class resembles a room that PUN joins (or joined). The properties are settable as opposed to those of a [RoomInfo](#) and you can close or hide "your" room.

9.23 C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking/Assets/Photon Unity Networking/Plugins/PhotonNetwork/RoomInfo.cs File Reference ↩

Classes

- class [RoomInfo](#)

A simplified room with just the info required to list and join, used for the room listing in the lobby. The properties are not settable (open, MaxPlayers, etc).

9.24 C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking/Assets/Photon Unity Networking/Plugins/PhotonNetwork/RPC.cs File Reference ↩

Reimplements a RPC Attribute, as it's no longer in all versions of the [UnityEngine](#) assembly.

Classes

- class [PunRPC](#)

Replacement for RPC attribute with different name. Used to flag methods as remote-callable.

9.24.1 Detailed Description

Reimplements a RPC Attribute, as it's no longer in all versions of the [UnityEngine](#) assembly.

9.25 C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking/Assets/Photon Unity Networking/Plugins/PhotonNetwork/ServerSettings.cs File Reference ↩

ScriptableObject defining a server setup. An instance is created as **PhotonServerSettings**.

Classes

- class [Region](#)
- class [ServerSettings](#)

Collection of connection-relevant settings, used internally by [PhotonNetwork.ConnectUsingSettings](#).

9.25.1 Detailed Description

ScriptableObject defining a server setup. An instance is created as **PhotonServerSettings**.

9.26 C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking/Assets/Photon Unity Networking/Plugins/PhotonNetwork/SocketWebTcp.cs File Reference ↩

9.27 C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking/Assets/Photon Unity Networking/Plugins/PhotonNetwork/Views/PhotonAnimatorView.cs File Reference ↩

Classes

- class [PhotonAnimatorView](#)

This class helps you to synchronize Mecanim animations. Simply add the component to your GameObject and make sure that the [PhotonAnimatorView](#) is added to the list of observed components.

- class [PhotonAnimatorView.SynchronizedParameter](#)
- class [PhotonAnimatorView.SynchronizedLayer](#)

9.28 C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking/Assets/Photon Unity Networking/Plugins/PhotonNetwork/Views/PhotonRigidbody2DView.cs File Reference ↩

Classes

- class [PhotonRigidbody2DView](#)

This class helps you to synchronize the velocities of a 2d physics Rigidbody. Note that only the velocities are synchronized and because Unity's physics engine is not deterministic (ie. the results aren't always the same on all computers) - the actual positions of the objects may go out of sync. If you want to have the position of this object the same on all clients, you should also add a [PhotonTransformView](#) to synchronize the position. Simply add the component to your GameObject and make sure that the [PhotonRigidbody2DView](#) is added to the list of observed components.

9.29 C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking/Assets/Photon Unity Networking/Plugins/PhotonNetwork/Views/PhotonRigidbodyView.cs File Reference ↩

Classes

- class [PhotonRigidbodyView](#)

This class helps you to synchronize the velocities of a physics Rigidbody. Note that only the velocities are synchronized and because Unity's physics engine is not deterministic (ie. the results aren't always the same on all computers) - the actual positions of the objects may go out of sync. If you want to have the position of this object the same on all clients, you should also add a [PhotonTransformView](#) to synchronize the position. Simply add the component to your GameObject and make sure that the [PhotonRigidbodyView](#) is added to the list of observed components.

9.30 C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking/Assets/Photon Unity Networking/Plugins/PhotonNetwork/Views/PhotonTransformView.cs File Reference ↩

Classes

- class [PhotonTransformView](#)

This class helps you to synchronize position, rotation and scale of a GameObject. It also gives you many different options to make the synchronized values appear smooth, even when the data is only sent a couple of times per second. Simply add the component to your GameObject and make sure that the [PhotonTransformView](#) is added to the list of observed components.

9.31 C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking/Assets/Photon Unity Networking/Plugins/PhotonNetwork/Views/PhotonTransformViewPositionControl.cs File Reference

Classes

- class [PhotonTransformViewPositionControl](#)

9.32 C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking/Assets/Photon Unity Networking/Plugins/PhotonNetwork/Views/PhotonTransformViewPositionModel.cs File Reference

Classes

- class [PhotonTransformViewPositionModel](#)

9.33 C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking/Assets/Photon Unity Networking/Plugins/PhotonNetwork/Views/PhotonTransformViewRotationControl.cs File Reference

Classes

- class [PhotonTransformViewRotationControl](#)

9.34 C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking/Assets/Photon Unity Networking/Plugins/PhotonNetwork/Views/PhotonTransformViewRotationModel.cs File Reference

Classes

- class [PhotonTransformViewRotationModel](#)

9.35 C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking/Assets/Photon Unity Networking/Plugins/PhotonNetwork/Views/PhotonTransformViewScaleControl.cs File Reference

Classes

- class [PhotonTransformViewScaleControl](#)

9.36 C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking/Assets/Photon Unity Networking/Plugins/PhotonNetwork/Views/PhotonTransformViewScaleModel.cs File Reference

Classes

- class [PhotonTransformViewScaleModel](#)

9.37 C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking/Assets/PhotonChatApi/ChatChannel.cs File Reference

Classes

- class [ExitGames.Client.Photon.Chat.ChatChannel](#)
A channel of communication in *Photon Chat*, updated by [ChatClient](#) and provided as *READ ONLY*.

Namespaces

- package [ExitGames.Client.Photon.Chat](#)

9.38 C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking/Assets/PhotonChatApi/ChatClient.cs File Reference

Classes

- class [ExitGames.Client.Photon.Chat.ChatClient](#)
Central class of the *Photon Chat* API to connect, handle channels and messages.

Namespaces

- package [ExitGames.Client.Photon.Chat](#)

9.39 C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking/Assets/PhotonChatApi/ChatDisconnectCause.cs File Reference

Namespaces

- package [ExitGames.Client.Photon.Chat](#)

Enumerations

- enum [ExitGames.Client.Photon.Chat.ChatDisconnectCause](#) {
[ExitGames.Client.Photon.Chat.ChatDisconnectCause.None](#), [ExitGames.Client.Photon.Chat.ChatDisconnectCause.DisconnectByServerUserLimit](#), [ExitGames.Client.Photon.Chat.ChatDisconnectCause.ExceptionOnConnect](#), [ExitGames.Client.Photon.Chat.ChatDisconnectCause.DisconnectByServer](#),
[ExitGames.Client.Photon.Chat.ChatDisconnectCause.TimeoutDisconnect](#), [ExitGames.Client.Photon.Chat.ChatDisconnectCause.Exception](#), [ExitGames.Client.Photon.Chat.ChatDisconnectCause.InvalidAuthentication](#), [ExitGames.Client.Photon.Chat.ChatDisconnectCause.MaxCcuReached](#),
[ExitGames.Client.Photon.Chat.ChatDisconnectCause.InvalidRegion](#), [ExitGames.Client.Photon.Chat.ChatDisconnectCause.OperationNotAllowedInCurrentState](#), [ExitGames.Client.Photon.Chat.ChatDisconnectCause.CustomAuthenticationFailed](#) }
Enumeration of causes for Disconnects (used in [LoadBalancingClient.DisconnectedCause](#)).

9.40 C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking/Assets/PhotonChatApi/ChatEventCode.cs File Reference ↩

Classes

- class [ExitGames.Client.Photon.Chat.ChatEventCode](#)
Wraps up internally used constants in [Photon Chat](#) events. You don't have to use them directly usually.

Namespaces

- package [ExitGames.Client.Photon.Chat](#)

9.41 C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking/Assets/PhotonChatApi/ChatOperationCode.cs File Reference ↩

Classes

- class [ExitGames.Client.Photon.Chat.ChatOperationCode](#)
Wraps up codes for operations used internally in [Photon Chat](#). You don't have to use them directly usually.

Namespaces

- package [ExitGames.Client.Photon.Chat](#)

9.42 C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking/Assets/PhotonChatApi/ChatParameterCode.cs File Reference ↩

Classes

- class [ExitGames.Client.Photon.Chat.ChatParameterCode](#)
Wraps up codes for parameters (in operations and events) used internally in [Photon Chat](#). You don't have to use them directly usually.

Namespaces

- package [ExitGames.Client.Photon.Chat](#)

9.43 C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking/Assets/PhotonChatApi/ChatPeer.cs File Reference ↩

Classes

- class [ExitGames.Client.Photon.Chat.ChatPeer](#)
Provides basic operations of the [Photon Chat](#) server. This internal class is used by public [ChatClient](#).
- class [ExitGames.Client.Photon.Chat.AuthenticationValues](#)
Container for user authentication in [Photon](#). Set AuthValues before you connect - all else is handled.
- class [ExitGames.Client.Photon.Chat.ParameterCode](#)

- class [ExitGames.Client.Photon.Chat.ErrorCode](#)
ErrorCode defines the default codes associated with [Photon](#) client/server communication.

Namespaces

- package [ExitGames.Client.Photon.Chat](#)

Enumerations

- enum [ExitGames.Client.Photon.Chat.CustomAuthenticationType](#) : byte {
[ExitGames.Client.Photon.Chat.CustomAuthenticationType.Custom](#) = 0, [ExitGames.Client.Photon.Chat.CustomAuthenticationType.Steam](#) = 1, [ExitGames.Client.Photon.Chat.CustomAuthenticationType.Facebook](#) = 2, [ExitGames.Client.Photon.Chat.CustomAuthenticationType.Oculus](#) = 3, [ExitGames.Client.Photon.Chat.CustomAuthenticationType.PlayStation](#) = 4, [ExitGames.Client.Photon.Chat.CustomAuthenticationType.Xbox](#) = 5, [ExitGames.Client.Photon.Chat.CustomAuthenticationType.None](#) = byte.MaxValue }
Options for optional "Custom Authentication" services used with [Photon](#). Used by OpAuthenticate after connecting to [Photon](#).

9.44 C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking/Assets/PhotonChatApi/ChatState.cs File Reference

Namespaces

- package [ExitGames.Client.Photon.Chat](#)

Enumerations

- enum [ExitGames.Client.Photon.Chat.ChatState](#) {
[ExitGames.Client.Photon.Chat.ChatState.Uninitialized](#), [ExitGames.Client.Photon.Chat.ChatState.ConnectingToNameServer](#), [ExitGames.Client.Photon.Chat.ChatState.ConnectedToNameServer](#), [ExitGames.Client.Photon.Chat.ChatState.Authenticating](#), [ExitGames.Client.Photon.Chat.ChatState.Authenticated](#), [ExitGames.Client.Photon.Chat.ChatState.DisconnectingFromNameServer](#), [ExitGames.Client.Photon.Chat.ChatState.ConnectingToFrontEnd](#), [ExitGames.Client.Photon.Chat.ChatState.ConnectedToFrontEnd](#), [ExitGames.Client.Photon.Chat.ChatState.DisconnectingFromFrontEnd](#), [ExitGames.Client.Photon.Chat.ChatState.QueuedComingFromFrontEnd](#), [ExitGames.Client.Photon.Chat.ChatState.Disconnecting](#), [ExitGames.Client.Photon.Chat.ChatState.Disconnected](#) }
Possible states for a LoadBalancingClient.

9.45 C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking/Assets/PhotonChatApi/ChatUserStatus.cs File Reference

Classes

- class [ExitGames.Client.Photon.Chat.ChatUserStatus](#)
Contains commonly used status values for SetOnlineStatus. You can define your own.

Namespaces

- package [ExitGames.Client.Photon.Chat](#)

9.46 C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking/Assets/PhotonChatApi/IChatClientListener.cs File Reference

Classes

- interface [ExitGames.Client.Photon.Chat.IChatClientListener](#)

Callback interface for [Chat](#) client side. Contains callback methods to notify your app about updates. Must be provided to new [ChatClient](#) in constructor

Namespaces

- package [ExitGames.Client.Photon.Chat](#)